

**Agilent U2701A/U2702A
USB Modular
Oscilloscopes**

**IVI-COM Programmer's
Reference for Visual Basic
.Net**



Agilent Technologies

Notices

© Agilent Technologies, Inc., 2009 — 2012

No part of this manual may be reproduced in any form or by any means (including electronic storage and retrieval or translation into a foreign language) without prior agreement and written consent from Agilent Technologies, Inc. as governed by United States and international copyright laws.

Manual Part Number

U2702-90035

Edition

Third Edition, August 13, 2012

Agilent Technologies, Inc.
5301 Stevens Creek Blvd.
Santa Clara, CA 95052 USA

Warranty

The material contained in this document is provided “as is,” and is subject to being changed, without notice, in future editions. Further, to the maximum extent permitted by applicable law, Agilent disclaims all warranties, either express or implied, with regard to this manual and any information contained herein, including but not limited to the implied warranties of merchantability and fitness for a particular purpose. Agilent shall not be liable for errors or for incidental or consequential damages in connection with the furnishing, use, or performance of this document or of any information contained herein. Should Agilent and the user have a separate written agreement with warranty terms covering the material in this document that conflict with these terms, the warranty terms in the separate agreement shall control.

Technology Licenses

The hardware and or software described in this document are furnished under a license and may be used or copied only in accordance with the terms of such license.

Restricted Rights Legend

U.S. Government Restricted Rights. Software and technical data rights granted to the federal government include only those rights customarily provided to end user customers. Agilent provides this customary commercial license in Software and technical data pursuant to FAR 12.211 (Technical Data) and 12.212 (Computer Software) and, for the Department of Defense, DFARS 252.227-7015 (Technical Data - Commercial Items) and DFARS 227.7202-3 (Rights in Commercial Computer Software or Computer Software Documentation).

Safety Notices

CAUTION

A **CAUTION** notice denotes a hazard. It calls attention to an operating procedure, practice, or the like that, if not correctly performed or adhered to, could result in damage to the product or loss of important data. Do not proceed beyond a **CAUTION** notice until the indicated conditions are fully understood and met.

WARNING

A **WARNING** notice denotes a hazard. It calls attention to an operating procedure, practice, or the like that, if not correctly performed or adhered to, could result in personal injury or death. Do not proceed beyond a **WARNING** notice until the indicated conditions are fully understood and met.

Contents

1 Introduction to IVI-COM

Getting Started 2

Installation Guide 3

General Guidelines for Oscilloscope Programming 5

Side-by-Side SCPI and IVI-COM Comparison of the U2701A/U2702A
Commands 6

2 Configuration

Count 12

Item 13

BandwidthLimit 13

Configure 15

Coupling 17

Enabled 19

Offset 21

ProbeAttenuation 23

Range 25

Name 27

Close 28

Initialize 29

Initialized 31

Configure 32

Coupling 33

Edge 35

Configure 35

Slope 37

Glitch	39
Condition	39
Configure	41
Polarity	43
Width	45
Holdoff	46
Modifier	47
Level	49
Source	50
Status	51
TV	52
Configure	52
Event	54
LineNumber	56
SignalFormat	57
Type	59
Width	60
Condition	60
Configure	62
Polarity	64
ThresholdHigh	66
ThresholdLow	67
Clear	68
ConfigureServiceRequest	69
Preset	71
Register	72
SerialPoll	74
TimeoutMilliseconds	75

WaitForOperationComplete	77
Disable	78
ErrorQuery	79
LockObject	80
Reset	81
ResetWithDefaults	82
SelfTest	83
UnlockObject	85
Enumeration Members	86
AgilentU2701AGlitchConditionEnum	86
AgilentU2701AGlitchPolarityEnum	87
AgilentU2701ASRQReasonEnum	87
AgilentU2701AStatusRegisterEnum	89
AgilentU2701AStatusSubRegisterEnum	90
AgilentU2701ATriggerCouplingEnum	91
AgilentU2701ATriggerModifierEnum	91
AgilentU2701ATriggerSlopeEnum	92
AgilentU2701ATriggerTypeEnum	93
AgilentU2701ATVSignalFormatEnum	94
AgilentU2701ATVTriggerEventEnum	95
AgilentU2701AVerticalCouplingEnum	96
AgilentU2701AWidthConditionEnum	97
AgilentU2701AWidthPolarityEnum	97

3 Acquisition

ConfigureRecord	100
Interpolation	102
NumberOfAverages	104
RecordLength	105

SampleMode 106
SampleRate 107
StartTime 108
TimePerRecord 109
Type 112
Enumeration Members 114
 AgilentU2701AAcquisitionStatusEnum 114
 AgilentU2701AAcquisitionTypeEnum 115
 AgilentU2701AInterpolationEnum 116
 AgilentU2701ASampleModeEnum 116

4 **Waveform Display**

Abort 118
AutoSetup 119
Count 120
Initiate 121
IsWaveformElementInvalid 122
Item 124
 FetchWaveform 124
 ReadWaveform 126

5 **Post Analysis**

Abort 130
AutoSetup 131
Count 132
Initiate 133
IsWaveformElementInvalid 134

Item	136
FetchWaveform	136
FetchWaveformMeasurement	138
ReadFullWaveform	140
ReadWaveform	142
ReadWaveformMeasurement	144
MathFunction	146
Name	147
Status	148
Enumeration Members	149
AgilentU2701AMathOperationEnum	149
AgilentU2701AMeasurementEnum	150
AgilentU2701ATimeOutEnum	153

6 Others

Calibrate	156
Date	157
Label	158
Time	159
Cache	160
ClearInterchangeWarnings	161
DriverSetup	162
GetNextCoercionRecord	163
GetNextInterchangeWarning	164
InterchangeCheck	165
InvalidateAllAttributes	166
IoResourceDescriptor	167

LogicalName	168
QueryInstrumentStatus	169
RangeCheck	170
RecordCoercions	171
ResetInterchangeCheck	172
Simulate	173
Description	174
GroupCapabilities	175
Identifier	176
InstrumentFirmwareRevision	177
InstrumentManufacturer	178
InstrumentModel	179
Revision	180
SpecificationMajorVersion	181
SpecificationMinorVersion	182
SupportedInstrumentModels	183
Vendor	184
SerialNumber	185

7 Application Example

Introduction	188
Referencing the Driver	188
Creating an Instance	188
Initializing the Driver	189
Complete Example	190



1 Introduction to IVI-COM

Getting Started	2
Installation Guide	3
General Guidelines for Oscilloscope Programming	5
Side-by-Side SCPI and IVI-COM Comparison of the U2701A/U2702A Commands	6

This chapter introduces the remote programming basics of the U2701A/U2702A USB modular oscilloscopes. The IVI-COM programming commands provide the means to control this instrument remotely via a PC.



Getting Started

The IVI Foundation is an open consortium founded in year 1998 to promote specifications for programming test instruments.

For complete information on the IVI Foundation and for the most up-to-date versions of all IVI specifications and components, you can visit the IVI Foundation web site at www.ivifoundation.org.

Installation Guide


- 1 To download the AgilentU2701A IVI Driver, go to the Agilent Technical Support web site at:
<http://www.home.agilent.com/agilent/techSupport.jsp?pid=1369621&cc=US&lc=eng&t=80029.k.0&guid=181735>
- 2 Click **Drivers & Software > IVI-COM and IVI-C for U2701A/U2702A** to download the AgilentU2701A IVI Driver package.
- 3 Save the file to any location on your hard disk.
- 4 Disconnect any instrument that is connected to your PC and close all other applications on your PC.
- 5 Double-click the saved installation file to begin installation.
- 6 The latest version of the IVI Shared Components should be downloaded from www.ivifoundation.org prior to installing the AgilentU2701A IVI Driver package. It is recommended that you periodically check for newer versions of the IVI Shared Components and update as available from the IVI Foundation.
- 7 If the latest version of the IVI Shared Components is detected, installation of the AgilentU2701A IVI Driver will proceed as normal.



- 8 The **AgilentU2701A IVI Driver 1.0.0.0 Setup Wizard** dialog will appear. Click **Next** to begin.
- 9 Read the License Agreement and select **I accept the terms in the License Agreement** to proceed. You may click **Print** to print a hardcopy of the Agilent License Terms for your reference. Click **Next** to proceed.
- 10 Fill in the Customer Information Form accordingly, and click **Next**.
- 11 Select the **Typical** or **Full** option in the Setup Type to install the AgilentU2701A IVI Driver package. Advanced users may select the **Custom** option to customize the program features to be installed and where they will be installed. Click **Next** to proceed.
- 12 Click **Next** to install to the specified folder or click **Change** to install to a different folder.
- 13 Click **Install** to begin the installation of the AgilentU2701A IVI Driver package.
- 14 Click **Finish** when the installation has completed.

General Guidelines for Oscilloscope Programming

The block diagram below illustrates the general flow of steps required to program an oscilloscope. The necessary IVI-COM driver commands are arranged to reflect this block diagram.



Side-by-Side SCPI and IVI-COM Comparison of the U2701A/U2702A Commands

Table 1-1 SCPI, IAgilentU2701A IVI, and IlviScope command comparison

SCPI command	IAgilentU2701A IVI command	IlviScope command
IEEE 488.2 Common commands		
*CLS	IAgilentU2701ASystem.Clear	-
*IDN	IlviDriver.Identity	IlviDriver.Identity
*OPC?	IAgilentU2701ASystem.WaitForOperationComplete()	-
*RST	IlviDriverUtility.Reset()	IlviDriverUtility.Reset()
Root level commands		
AUTO	IAgilentU2701AMeasurements.AutoSetup	IlviScopeMeasurements.AutoSetup
ACQuire commands		
AVERages	IAgilentU2701AAcquisition.NumberOfAverages	IlviScopeAcquisition.NumberOfAverages
MODE	IAgilentU2701AAcquisition.SampleMode	IlviScopeAcquisition.SampleMode
SRATE?	IAgilentU2701AAcquisition.SampleRate	IlviScopeAcquisition.SampleRate
TYPE	IAgilentU2701AAcquisition.Type	IlviScopeAcquisition.Type
CHANnel<n> commands		
BWLimit	IAgilentU2701AChannel.BandwidthLimit	-
COUPling	IAgilentU2701AChannel.Coupling	IlviScopeChannel.Coupling
DISPlay	IAgilentU2701AChannel.Enabled	IlviScopeChannel.Enabled
INVert	-	-
OFFSet	IAgilentU2701AChannel.Offset	IlviScopeChannel.Offset
PROBE	IAgilentU2701AChannel.ProbeAttenuation	IlviScopeChannel.ProbeAttenuation
SCALE	IAgilentU2701AChannel.Range	IlviScopeChannel.Range

Table 1-1 SCPI, IAgilentU2701A IVI, and IlviScope command comparison

SCPI command	IAgilentU2701A IVI command	IlviScope command
KEY commands		
AUTO_SCALE	IAgilentU2701AMeasurements.AutoSetup	IlviScopeMeasurements.AutoSetup
CH1	IAgilentU2701AChannel.Enabled	IlviScopeChannel.Enabled
CH1_POS_DEC	IAgilentU2701AChannel.Offset	IlviScopeChannel.Offset
CH1_POS_INC	IAgilentU2701AChannel.Offset	IlviScopeChannel.Offset
CH1_SCALE_DEC	IAgilentU2701AChannel.Range	IlviScopeChannel.Range
CH1_SCALE_INC	IAgilentU2701AChannel.Range	IlviScopeChannel.Range
CH2	IAgilentU2701AChannel.Enabled	IlviScopeChannel.Enabled
CH2_POS_DEC	IAgilentU2701AChannel.Offset	IlviScopeChannel.Offset
CH2_POS_INC	IAgilentU2701AChannel.Offset	IlviScopeChannel.Offset
CH2_SCALE_DEC	IAgilentU2701AChannel.Range	IlviScopeChannel.Range
CH2_SCALE_INC	IAgilentU2701AChannel.Range	IlviScopeChannel.Range
MAIN_DELAYED	IAgilentU2701AAcquisition.StartTime	IlviScopeAcquisition.StartTime
MATH	IAgilentU2701AMeasurementsMathFunction	-
MEASURE	IAgilentU2701AMeasurement	IlviScope.Measurement
MODE_COUPLING	IAgilentU2701AChannel.Coupling	IlviScopeChannel.Coupling
SINGLE	IAgilentU2701AMeasurements.Initiate	IlviScopeMeasurements.Initiate
TIME_POS_DEC	IAgilentU2701AAcquisition.StartTime	IlviScopeAcquisition.StartTime
TIME_POS_INC	IAgilentU2701AAcquisition.StartTime	IlviScopeAcquisition.StartTime
TIME_SCALE_DEC	IAgilentU2701AAcquisition.TimePerRecord	IlviScopeAcquisition.TimePerRecord
TIME_SCALE_INC	IAgilentU2701AAcquisition.TimePerRecord	IlviScopeAcquisition.TimePerRecord
TRIG_LVL_DEC	IAgilentU2701ATrigger.Level Property	IlviScopeTrigger.Level
TRIG_LVL_INC	IAgilentU2701ATrigger.Level Property	IlviScopeTrigger.Level

Table 1-1 SCPI, IAgilentU2701A IVI, and IIVI Scope command comparison

SCPI command	IAgilentU2701A IVI command	IIVI Scope command
MEASure commands		
FALLtime	AgilentU2701AMeasurementEnum Enumeration	IIVI ScopeMeasurementEnum Enumeration
FREQuency	AgilentU2701AMeasurementEnum Enumeration	IIVI ScopeMeasurementEnum Enumeration
NDUTycle	AgilentU2701AMeasurementEnum Enumeration	IIVI ScopeMeasurementEnum Enumeration
NWIDth	AgilentU2701AMeasurementEnum Enumeration	IIVI ScopeMeasurementEnum Enumeration
OVERshoot	AgilentU2701AMeasurementEnum Enumeration	IIVI ScopeMeasurementEnum Enumeration
PDUtycle	AgilentU2701AMeasurementEnum Enumeration	IIVI ScopeMeasurementEnum Enumeration
PERiod	AgilentU2701AMeasurementEnum Enumeration	IIVI ScopeMeasurementEnum Enumeration
PREShoot	AgilentU2701AMeasurementEnum Enumeration	IIVI ScopeMeasurementEnum Enumeration
PWIDth	AgilentU2701AMeasurementEnum Enumeration	IIVI ScopeMeasurementEnum Enumeration
RISetime	AgilentU2701AMeasurementEnum Enumeration	IIVI ScopeMeasurementEnum Enumeration
VAMPLitude	AgilentU2701AMeasurementEnum Enumeration	IIVI ScopeMeasurementEnum Enumeration
VAVerage	AgilentU2701AMeasurementEnum Enumeration	IIVI ScopeMeasurementEnum Enumeration
VBASe	AgilentU2701AMeasurementEnum Enumeration	IIVI ScopeMeasurementEnum Enumeration
VMAX	AgilentU2701AMeasurementEnum Enumeration	IIVI ScopeMeasurementEnum Enumeration
VMIN	AgilentU2701AMeasurementEnum Enumeration	IIVI ScopeMeasurementEnum Enumeration

Table 1-1 SCPI, IAgilentU2701A IVI, and IIVI Scope command comparison

SCPI command	IAgilentU2701A IVI command	IIVI Scope command
MEASure commands		
VPP	IAgilentU2701AMeasurementEnum Enumeration	IIVI ScopeMeasurementEnum Enumeration
VRMS	IAgilentU2701AMeasurementEnum Enumeration	IIVI ScopeMeasurementEnum Enumeration
VTOP	IAgilentU2701AMeasurementEnum Enumeration	IIVI ScopeMeasurementEnum Enumeration
TIMebase commands		
DELayed	IAgilentU2701AAcquisition.StartTime	IIVI ScopeAcquisition.StartTime
HOLDoff	IAgilentU2701ATrigger.Holdoff	IIVI ScopeTrigger.Holdoff
POSition	IAgilentU2701AAcquisition.StartTime	IIVI ScopeAcquisition.StartTime
SCALE	IAgilentU2701AAcquisition.TimePerRecord	IIVI ScopeAcquisition.TimePerRecord
TRIGger commands		
[EDGE]:COUPling	IAgilentU2701ATrigger.Coupling Property	IIVI ScopeChannel.Coupling
[EDGE]:LEVEl	IAgilentU2701ATrigger.Level Property	IIVI ScopeTrigger.Level
[EDGE]:SLOPe	IAgilentU2701ATriggerEdge.Slope Property	IIVI ScopeTriggerEdge.Slope
[EDGE]:SOURe	IAgilentU2701ATrigger.Source Property	IIVI ScopeTrigger.Source
[EDGE]:SWEep	IAgilentU2701ATrigger.Modifier Property	IIVI ScopeTrigger.Modifier
MODE	IAgilentU2701ATrigger.Type Property	IIVI ScopeTrigger.Type
PULSE:MODE	IAgilentU2701ATriggerTypeEnum Enumeration	IIVI ScopeTriggerTypeEnum Enumeration
PULSEe:WIDTh	IAgilentU2701ATriggerTypeEnum Enumeration	IIVI ScopeTriggerTypeEnum Enumeration
STATus	IAgilentU2701ATrigger.Status	-
WAVEform commands		
DATA?	IAgilentU2701AMeasurement.ReadWaveform	IIVI ScopeMeasurement.ReadWaveform
XINCrement?	IAgilentU2701AMeasurement.ReadWaveform	IIVI ScopeMeasurement.ReadWaveform
XORigin?	IAgilentU2701AMeasurement.ReadWaveform	IIVI ScopeMeasurement.ReadWaveform

1 Introduction to IVI-COM



2 Configuration

Channels Interface commands starting on [page 12](#)

Close [28](#)

Initialize [29](#)

Initialized [31](#)

Trigger Interface commands starting on [page 33](#)

Status Interface commands starting on [page 68](#)

System Interface commands starting on [page 75](#)

Utility Interface commands starting on [page 78](#)

Enumeration Members [86](#)

This chapter describes the configuration commands used to program the U2701A/U2702A USB modular oscilloscopes over the remote interface. You can use the commands in this chapter to configure the oscilloscope channels for waveform acquisition, set the type of event that triggers the oscilloscope, modify the registry status, and perform various utility operations.



Count

Type

Property

Function

Get

Description

This command returns the number of channels available.

Hierarchy

```
IAgilentU2701A
  | Channels
    | Count
```

Parameters

Long/Int32

Example

```
Sub Main()
    ' Create an instance of the driver
    Dim Driver As New AgilentU2701A
    ' Count Statement
    Dim Count As Int32
    Count = Driver.Channels.Count
End Sub
```

Item

This is an interface reference pointer to the IAgilentU2701AChannel interface which is selected by the channel name.

BandwidthLimit

Type

Property

Function

Get and Set

Description

This command returns/sets the bandwidth limit status for the selected channel. If `True`, the bandwidth limit for the selected channel is enabled. If `False`, the bandwidth limit for the selected channel is disabled.

Hierarchy

```

IAgilentU2701A
├── Channels
│   ├── Item(Name)
│   └── BandwidthLimit

```

Parameters

Item	Type	Description
Name	String	The name of a measurement. This command is used to select the channel the function is to be run on. (For example: Channel 1, Channel 2, and so on.)

Return Format

Boolean

Example

```
Sub Main()  
    ' Create an instance of the driver  
    Dim Driver As New AgilentU2701A  
    ' BandwidthLimit Statement  
    ' To Get Bandwidth Limit from the Instrument  
    Dim BandwidthLimit As Boolean  
    BandwidthLimit =  
        Driver.Channels.Item("Channel1").BandwidthLimit  
    ' To Set Bandwidth Limit eg. True  
    Driver.Channels.Item("Channel1").BandwidthLimit = True  
End Sub
```

Configure

Type

Method

Function

Set

Description

This command configures the most commonly used properties of the oscilloscope channel sub-system. Use this command to enable or disable the channel and to set the range, offset, coupling, and probe attenuation values.

Hierarchy

```
IAgilentU2701A
├── Channels
│   ├── Item(Name)
│   │   └── Configure(Range, Offset, Coupling, ProbeAttenuation,
│   │               Enabled)
```

Parameters

Item	Type	Description
Name	String	The name of a measurement. This command is used to select the channel the function is to be run on. (For example: Channel 1, Channel 2, and so on.)
Range	Double	Specifies the vertical range. This value sets the Vertical Range property.
Offset	Double	Specifies the vertical offset. This value sets the Vertical Offset property.
Coupling	AgilentU2701A VerticalCoupling Enum	Specifies how to couple the input signal. This value sets the Vertical Coupling property.
ProbeAttenuation	Double	Specifies the probe attenuation. This value sets the ProbeAttenuation property.
Enabled	Boolean	Specifies if the channel is enabled for acquisition. This value sets the Channels. Enabled property.

Return Format

Boolean

Example

```
Sub Main()  
    ' Create an instance of the driver  
    Dim Driver As New AgilentU2701A  
    ' Configure Statement  
    Dim BandwidthLimit As Boolean  
    Driver.Channels.Item("Channel1").Configure(40.0, 0.0,  
        AgilentU2701AVerticalCouplingEnum.AgilentU2701AVerticalCoupl  
        ingDC, 1.0, True)  
End Sub
```


Coupling

Type

Property

Function

Get and Set

Description

This command returns/sets how the oscilloscope couples the input signal.

Hierarchy

```
IAgilentU2701A
  | Channels
  |   | Item(Name)
  |   |   | Coupling
```

Parameters

Item	Type	Description
Name	String	The name of a measurement. This command is used to select the channel the function is to be run on. (For example: Channel 1, Channel 2, and so on.)

Return Format

Item	Type	Description
AgilentU2701A VerticalCoupling Enum	Enum	See " AgilentU2701AVerticalCouplingEnum " on page 96.

Example

```
Sub Main()  
    ' Create an instance of the driver  
    Dim Driver As New AgilentU2701A  
    ' Coupling Statement  
    ' To Get Coupling from the Instrument  
    Dim Coupling As New AgilentU2701AVerticalCouplingEnum  
    Coupling = Driver.Channels.Item("Channel1").Coupling  
    ' To Set Coupling eg. DC  
    Driver.Channels.Item("Channel1").Coupling =  
        AgilentU2701AVerticalCouplingEnum.AgilentU2701AVerticalCoupl  
        ingDC  
End Sub
```

Enabled

Type

Property

Function

Get and Set

Description

If this command is set to True, the oscilloscope acquires a waveform for this channel when the `IAgilentU2701AMeasurement.Initiate`, `IAgilentU2701AMeasurement.ReadWaveform`, `IAgilentU2701AMeasurement.ReadWaveformMeasurement`, or `IviScopeMeasurement.ReadWaveformMinMax` methods are called.

Hierarchy

```
IAgilentU2701A
├── Channels
│   ├── Item(Name)
│   └── Enabled
```

Parameters

Item	Type	Description
Name	String	The name of a measurement. This command is used to select the channel the function is to be run on. (For example: Channel 1, Channel 2, and so on.)

Return Format

Boolean

2 Configuration

Example

```
Sub Main()  
    ' Create an instance of the driver  
    Dim Driver As New AgilentU2701A  
    ' Enabled Statement  
    ' To Get Enabled from the Instrument  
    Dim Enabled As Boolean  
  
    Enabled = Driver.Channels.Item("Channel1").Enabled  
    ' To Set Enabled eg. True  
    Driver.Channels.Item("Channel1").Enabled = True  
End Sub
```

Offset

Type

Property

Function

Get and Set

Description

This command returns/sets the location of the center of the range that was specified with the [Range](#) property. The units are expressed in volts, with respect to ground. For example, to acquire a sine wave spanning from 0.0 V to 10.0 V, set Offset to 5.0 V.

Hierarchy

```
IAgilentU2701A
  | Channels
    | Item(Name)
      | Offset
```

Parameters

Item	Type	Description
Name	String	The name of a measurement. This command is used to select the channel the function is to be run on. (For example: Channel 1, Channel 2, and so on.)

Return Format

Double

2 Configuration

Example

```
Sub Main()  
    ' Create an instance of the driver  
    Dim Driver As New AgilentU2701A  
    ' Offset Statement  
    ' To Get Offset from the Instrument  
    Dim Offset As Double  
    Offset = Driver.Channels.Item("Channel1").Offset  
    ' To Set Offset eg. 0.0  
    Driver.Channels.Item("Channel1").Offset = 0.0  
End Sub
```

ProbeAttenuation

Type

Property

Function

Get and Set

Description

This command returns/sets the scaling factor by which the probe attenuates the input signal. For example, with a 10:1 probe, the value is 10.0.

Hierarchy

```
IAgilentU2701A
  | Channels
    | Item(Name)
      | ProbeAttenuation
```

Parameters

Item	Type	Description
Name	String	The name of a measurement. This command is used to select the channel the function is to be run on. (For example: Channel 1, Channel 2, and so on.)

Return Format

Double

2 Configuration

Example

```
Sub Main()  
    ' Create an instance of the driver  
    Dim Driver As New AgilentU2701A  
    ' ProbeAttenuation Statement  
    ' To Get ProbeAttenuation from the Instrument  
    Dim ProbeAttenuation As Double  
    ProbeAttenuation =  
        Driver.Channels.Item("Channel1").ProbeAttenuation  
    ' To Set ProbeAttenuation eg. 1.0  
    Driver.Channels.Item("Channel1").ProbeAttenuation = 1.0  
End Sub
```


Range

Type

Property

Function

Get and Set

Description

This command returns/sets the absolute value of the input range that the oscilloscope can acquire for the channel. The units are expressed in volts. For example, to acquire a sine wave spanning from -5.0 V to 5.0 V, set Range to 10.0 V.

Hierarchy

```
IAgilentU2701A
  | Channels
    | Item(Name)
      | Range
```

Parameters

Item	Type	Description
Name	String	The name of a measurement. This command is used to select the channel the function is to be run on. (For example: Channel 1, Channel 2, and so on.)

Remarks

The absolute value of the input range that the oscilloscope can acquire is equivalent to the Volt/Div value multiplied by eight at the scope setting.

Volt/Div (Attenuation = 1x)	Voltage range
2 mV	16 mV
5 mV	40 mV
10 mV	80 mV
20 mV	160 mV
50 mV	400 mV
100 mV	800 mV
200 mV	1.6 V
500 mV	4 V
1 V	8 V
2 V	16 V
5 V	40 V

Return Format

Double

Example

```
Sub Main()  
    ' Create an instance of the driver  
    Dim Driver As New AgilentU2701A  
    ' Range Statement  
    ' To Get Range from the Instrument  
    Dim Range As Double  
    Range = Driver.Channels.Item("Channel1").Range  
    ' To Set Range eg. 40  
    Driver.Channels.Item("Channel1").Range = 40  
End Sub
```

Name

Type

Property

Function

Get

Description

This command returns the channel name for a given index.

Hierarchy

```
IAgilentU2701A
  | Channels
    | Name(Index)
```

Parameters

Item	Type	Description
Index	Long/Int32	One based index into the collection of channels.

Return Format

String

Example

```
Sub Main()
    ' Create an instance of the driver
    Dim Driver As New AgilentU2701A
    ' Name Statement
    Dim Name As String
    Name = Driver.Channels.Name(1)
End Sub
```

Close

Type

Method

Function

Set

Description

This command closes the I/O session to the instrument. Driver methods and properties that access the instrument are not accessible after Close is called.

Hierarchy

```
IAgilentU2701A
├ Close()
```

Example

```
Sub Main()
    ' Create an instance of the driver
    Dim Driver As New AgilentU2701A
    'Close Statement
    Driver.Close()
End Sub
```

Initialize

Type

Method

Function

Set

Description

This command opens the I/O session to the instrument. Driver methods and properties that access the instrument are only accessible after Initialize is called. Initialize optionally performs a Reset and queries the instrument to validate the instrument model.

Hierarchy

IAgilentU2701A

└ Initialize(ResourceName, IdQuery, Reset, OptionString)

Parameters

Item	Type	Description
ResourceName	String/BSTR	An IVI logical name or an instrument specific string that identifies the address of the instrument, such as a VISA resource descriptor string.
IdQuery	Boolean	Specifies whether to verify the ID of the instrument.
Reset	Boolean	Specifies whether to reset the instrument.
OptionString	String/BSTR	<p>The user can use the <i>OptionString</i> parameter to specify the initial values of certain IVI inherent attributes for the session.</p> <p>The format of an assignment in the <i>OptionString</i> parameter is "Name=Value", where <i>Name</i> is one of: RangeCheck, QueryInstrumentStatus, Cache, Simulate, RecordCoercions, InterchangeCheck, or DriverSetup.</p> <p>Value is either True or False except for DriverSetup. If the <i>OptionString</i> parameter contains an assignment for the Driver Setup attribute, the Initialize function assumes that everything following "DriverSetup=" is part of the assignment.</p>

Example

```

Sub Main()
    ' Create an instance of the driver
    Dim Driver As New AgilentU2701A
    ' Initialize Statement
    Driver.Initialize("USB0::2391::10520::MY48151002::0::INSTR",
        True, True, "")
End Sub

```

Initialized

Type

Property

Function

Get

Description

This command returns `True` between a successful call to the [Initialize](#) method and a successful call to the [Close](#) method, and `False` at all other times.

Hierarchy

```
IAgilentU2701A
└─ Initialized
```

Return Format

Boolean

Example

```
Sub Main()
    ' Create an instance of the driver
    Dim Driver As New AgilentU2701A
    ' Initialized Statement
    Dim Initialized As Boolean
    Initialized = Driver.Initialized
End Sub
```

Configure

Type

Method

Function

Set

Description

This command configures the trigger *Type* and *Holdoff*. *Holdoff* units are expressed in seconds.

Hierarchy

```
IAgilentU2701A
├ Trigger
│   └ Configure(Type, Holdoff)
```

Parameters

Item	Type	Description
Type	AgilentU2701A TriggerTypeEnum	Specifies the trigger type. This value sets the Trigger.Type property. See “AgilentU2701ATriggerTypeEnum” on page 93 for more information.
Holdoff	Double	Specifies the trigger hold-off. This value sets the Trigger.Holdoff property.

Example

```
Sub Main()
    ' Create an instance of the driver
    Dim Driver As New AgilentU2701A
    ' Configure Statement
    Driver.Trigger.Configure(AgilentU2701ATriggerTypeEnum.Agilent
        U2701ATriggerEdge, 5)
End Sub
```


Coupling

Type

Property

Function

Get and Set

Description

This command returns/sets how the oscilloscope couples the trigger source.

Hierarchy

```
IAgilentU2701A
  |
  | Trigger
  |
  | Coupling
```

Return Format

Item	Type	Description
AgilentU2701A TriggerCoupling Enum	Enum	See " AgilentU2701ATriggerCouplingEnum " on page 91 for more information.

Example

```
Sub Main()  
    ' Create an instance of the driver  
    Dim Driver As New AgilentU2701A  
    ' Coupling Statement  
    ' To Get Coupling from the Instrument  
    Dim Coupling As AgilentU2701ATriggerCouplingEnum  
    Coupling = Driver.Trigger.Coupling  
    ' To Set Coupling eg. AC  
    Driver.Trigger.Coupling =  
        AgilentU2701ATriggerCouplingEnum.AgilentU2701ATriggerCouplin  
        gAC  
End Sub
```

Edge

This interface configures slope of edge trigger.

Configure

Type

Method

Function

Set

Description

This command configures the conditions for edge trigger. An edge trigger occurs when the trigger source signal passes through the trigger level with the specified slope.

Hierarchy

```
IAgilentU2701A
├ Trigger
│   └ Edge
│       └ Configure(Source, Level, Slope)
```

Parameters

Item	Type	Description
Source	String	Specifies the trigger source. This value sets the <code>Trigger.Source</code> property.
Level	Double	Specifies the trigger level. This value sets the <code>Trigger.Level</code> property.
Slope	AgilentU2701A TriggerSlopeEnum	Specifies the trigger slope. This value sets the <code>Trigger.Slope</code> property. See “AgilentU2701ATriggerSlopeEnum” on page 92 for more information.

Example

```
Sub Main()  
    ' Create an instance of the driver  
    Dim Driver As New AgilentU2701A  
    ' Configure Statement  
    Driver.Trigger.Edge.Configure("Channel1", 0,  
        AgilentU2701ATriggerSlopeEnum.AgilentU2701ATriggerSlopePositive)  
End Sub
```

Slope

Type

Property

Function

Get and Set

Description

This command returns/sets the slope, a rising or a falling edge, that triggers the oscilloscope.

Hierarchy

```

IAgilentU2701A
  |
  | L Trigger
  |   |
  |   | L Edge
  |   |   |
  |   |   | L Slope
  
```

Parameters

Item	Type	Description
AgilentU2701A TriggerSlopeEnum	Enum	See “AgilentU2701ATriggerSlopeEnum” on page 92 for more information.

Example

```
Sub Main()  
    ' Create an instance of the driver  
    Dim Driver As New AgilentU2701A  
    ' Slope Statement  
    ' To Get Slope from the Instrument  
    Dim Slope As AgilentU2701ATriggerSlopeEnum  
    Slope = Driver.Trigger.Edge.Slope  
    ' To Set Slope eg. AC  
    Driver.Trigger.Edge.Slope =  
        AgilentU2701ATriggerSlopeEnum.AgilentU2701ATriggerSlopePosit  
        ive  
End Sub
```

Glitch

This interface configures the condition, polarity, and width of the glitch trigger.

Condition

Type

Property

Function

Get and Set

Description

This command returns/sets the glitch condition that determines whether the oscilloscope triggers on a pulse with a width less than or greater than the glitch width value.

Hierarchy

```
IAgilentU2701A
  |
  | Trigger
  |   |
  |   | Glitch
  |   |   |
  |   |   | Condition
```

Parameters

Item	Type	Description
AgilentU2701A GlitchCondition Enum	Enum	See " AgilentU2701AGlitchConditionEnum " on page 86 for more information.

2 Configuration

Example

```
Sub Main()  
    ' Create an instance of the driver  
    Dim Driver As New AgilentU2701A  
    ' Condition Statement  
    ' To Get Condition from the Instrument  
    Dim Condition As AgilentU2701AGlitchConditionEnum  
    Condition = Driver.Trigger.Glitch.Condition  
    ' To Set Condition eg. Greater Than  
    Driver.Trigger.Glitch.Condition =  
        AgilentU2701AGlitchConditionEnum.AgilentU2701AGlitchConditio  
        nGreaterThan  
End Sub
```


Configure

Type

Method

Function

Set

Description

This command configures the glitch trigger *Source*, *Level*, *Width*, *Polarity*, and *Condition*. A glitch trigger occurs when the edge of a pulse that matches the *Width* and *Polarity* crosses the specified *Level* (expressed in volts).

Hierarchy

```
IAgilentU2701A
├ Trigger
│   └ Glitch
│       └ Configure(Source, Level, Width, Polarity, Condition)
```

Parameters

Item	Type	Description
Source	String	Specifies the trigger source. This value sets the <code>Trigger.Source</code> property.
Level	Double	Specifies the trigger level. This value sets the <code>Trigger.Level</code> property.
Width	Double	Specifies the glitch triggering glitch width in seconds. This value sets the <code>Glitch.Width</code> property.
Polarity	AgilentU2701A GlitchPolarity Enum	Specifies the glitch polarity. This value sets the <code>Glitch.Polarity</code> property.
Condition	AgilentU2701A GlitchCondition Enum	Specifies the glitch condition. This value sets the <code>Glitch.Condition</code> property.

Example

```
Sub Main()  
    ' Create an instance of the driver  
    Dim Driver As New AgilentU2701A  
    ' Configure Statement  
    Driver.Trigger.Glitch.Configure("Channel1", 0, 0.00000003,  
        AgilentU2701AGlitchPolarityEnum.AgilentU2701AGlitchPolarityP  
        ositive,  
        AgilentU2701AGlitchConditionEnum.AgilentU2701AGlitchConditio  
        nGreaterThan)  
End Sub
```

Polarity

Type

Property

Function

Get and Set

Description

This command returns/sets the polarity of the glitch that triggers the oscilloscope.

Hierarchy

```
IAgilentU2701A
  |
  | L Trigger
  |   |
  |   | L Glitch
  |   |   |
  |   |   | L Polarity
```

Return Format

Item	Type	Description
AgilentU2701A GlitchPolarity Enum	Enum	Specifies the glitch polarity. This value sets the Glitch.Polarity property.

Example

```
Sub Main()  
    ' Create an instance of the driver  
    Dim Driver As New AgilentU2701A  
    ' Polarity Statement  
    ' To Get Polarity from the Instrument  
    Dim Polarity As AgilentU2701AGlitchPolarityEnum  
    Polarity = Driver.Trigger.Glitch.Polarity  
    ' To Set Polarity eg. Positive  
    Driver.Trigger.Glitch.Polarity =  
        AgilentU2701AGlitchPolarityEnum.AgilentU2701AGlitchPolarityP  
        ositive  
End Sub
```

Width

Type

Property

Function

Get and Set

Description

This command returns/sets the glitch width. The units are expressed in seconds.

Hierarchy

```
IAgilentU2701A
├── Trigger
│   ├── Glitch
│   │   └── Width
```

Return Format

Double

Example

```
Sub Main()
    ' Create an instance of the driver
    Dim Driver As New AgilentU2701A
    ' Width Statement
    ' To Get Width from the Instrument
    Dim Width As Double
    Width = Driver.Trigger.Glitch.Width
    ' To Set Width eg. 0.00000003
    Driver.Trigger.Glitch.Width = 0.00000003
End Sub
```

Holdoff

Type

Property

Function

Get and Set

Description

This command returns/sets the length of time the oscilloscope waits after it fills the acquisition buffer until the oscilloscope enables the trigger interface to detect another trigger. The units are expressed in seconds.

Hierarchy

```
IAgilentU2701A
├─ Trigger
│  └─ Holdoff
```

Return Format

Double

Example

```
Sub Main()
    ' Create an instance of the driver
    Dim Driver As New AgilentU2701A
    ' Holdoff Statement
    ' To Get Holdoff from the Instrument
    Dim Holdoff As Double
    Holdoff = Driver.Trigger.Holdoff
    ' To Set Holdoff eg. 0.00000006
    Driver.Trigger.Holdoff = 0.00000006
End Sub
```

Modifier

Type

Property

Function

Get and Set

Description

This command determines the oscilloscope behavior in the absence of a trigger.

Hierarchy

```
IAgilentU2701A
  └ Trigger
    └ Modifier
```

Return Format

Item	Type	Description
AgilentU2701A TriggerModifier Enum	Enum	See " AgilentU2701ATriggerModifierEnum " on page 91 for more information.

Example

```
Sub Main()  
    ' Create an instance of the driver  
    Dim Driver As New AgilentU2701A  
    ' Modifier Statement  
    ' To Get Modifier from the Instrument  
    Dim Modifier As AgilentU2701ATriggerModifierEnum  
    Modifier = Driver.Trigger.Modifier  
    ' To Set Modifier eg. Auto  
    Driver.Trigger.Modifier =  
        AgilentU2701ATriggerModifierEnum.AgilentU2701ATriggerModifie  
        rAuto  
End Sub
```


Level

Type

Property

Function

Get and Set

Description

This command returns/sets the voltage threshold for the trigger interface. The units are expressed in volts.

Hierarchy

```
IAgilentU2701A
  |
  | Trigger
  |   |
  |   | Level
```

Return Format

Double

Example

```
Sub Main()
    ' Create an instance of the driver
    Dim Driver As New AgilentU2701A
    ' Level Statement
    ' To Get Level from the Instrument
    Dim Level As Double
    Level = Driver.Trigger.Level
    ' To Set Level eg. 0
    Driver.Trigger.Level = 0
End Sub
```

Source

Type

Property

Function

Get and Set

Description

This command returns/sets the signal that the oscilloscope monitors for a trigger. It can be a channel or one of many other values.

Hierarchy

```
IAgilentU2701A
  | Trigger
  | Source
```

Return Format

String/BSTR

Example

```
Sub Main()
    ' Create an instance of the driver
    Dim Driver As New AgilentU2701A
    ' Source Statement
    ' To Get Source from the Instrument
    Dim Source As String
    Source = Driver.Trigger.Source
    ' To Set Source eg. Channel1
    Driver.Trigger.Source = "Channel1"
End Sub
```

Status

Type

Property

Function

Get

Description

If this command is set to `True`, the waveform starts directly after the trigger condition is met. If this command is set to `False`, the instrument has to send a force trigger to get a waveform.

Hierarchy

```
IAgilentU2701A
├─ Trigger
│  └─ Status
```

Return Format

Boolean

Example

```
Sub Main()
    ' Create an instance of the driver
    Dim Driver As New AgilentU2701A
    ' Status Statement
    Dim Status As Boolean
    Status = Driver.Trigger.Status
End Sub
```

TV

This interface configures the signal format, number of lines, and events of the TV trigger.

Configure

Type

Method

Function

Set

Description

This command configures the TV trigger source, signal format, event, and polarity.

Hierarchy

```
IAgilentU2701A
├─ Trigger
│   └─ TV
│       └─ Configure(Source, SignalFormat, Event)
```

Parameters

Item	Type	Description
Source	String	Specifies the trigger source. This value sets the <code>Trigger.Source</code> property.
SignalFormat	AgilentU2701ATV SignalFormat Enum	Specifies the TV trigger signal format. This value sets the <code>TV.SignalFormat</code> property. See “AgilentU2701ATVSignalFormatEnum” on page 94 for more information.
Event	AgilentU2701ATV TriggerEventEnum	Specifies the TV trigger event. This value sets the <code>TV.Event</code> property. See “AgilentU2701ATVTriggerEventEnum” on page 95 for more information.

Example

```

Sub Main()
    ' Create an instance of the driver
    Dim Driver As New AgilentU2701A
    ' Configure Statement
    Driver.Trigger.TV.Configure("Channell",
        AgilentU2701ATVSignalFormatEnum.AgilentU2701ATVSignalFormatN
        TSC,
        AgilentU2701ATVTriggerEventEnum.AgilentU2701ATVTriggerEventA
        nyField)
End Sub

```

Event

Type

Property

Function

Get and Set

Description

This command returns/sets the event on which the oscilloscope triggers.

Hierarchy

```
IAgilentU2701A
  |
  | L Trigger
  |   |
  |   | L TV
  |   |   |
  |   |   | L Event
```

Return Format

Item	Type	Description
AgilentU2701ATV TriggerEventEnum	Enum	See “AgilentU2701ATVTriggerEventEnum” on page 95 for more information.

Example

```
Sub Main()  
    ' Create an instance of the driver  
    Dim Driver As New AgilentU2701A  
    ' Event Statement  
    ' To Get Event from the Instrument  
    Dim TVEvent As AgilentU2701ATVTriggerEventEnum  
    TVEvent = Driver.Trigger.TV.Event  
    ' To Set Event eg. Channell1  
    Driver.Trigger.TV.Event =  
        AgilentU2701ATVTriggerEventEnum.AgilentU2701ATVTriggerEventA  
        nyField  
End Sub
```

LineNumber

Type

Property

Function

Get and Set

Description

This command returns/sets the line on which the oscilloscope triggers. The line number is absolute and not relative to the field of the TV signal.

Hierarchy

```
IAgilentU2701A
├── Trigger
│   ├── TV
│   │   └── LineNumber
```

Return Format

Long/Int32

Example

```
Sub Main()
    ' Create an instance of the driver
    Dim Driver As New AgilentU2701A
    ' LineNumber Statement
    ' To Get LineNumber from the Instrument
    Dim LineNumber As Int32
    LineNumber = Driver.Trigger.TV.LineNumber
    ' To Set LineNumber eg. 1
    Driver.Trigger.TV.LineNumber = 1
End Sub
```


SignalFormat

Type

Property

Function

Get and Set

Description

This command returns/sets the format of the TV signal on which the oscilloscope triggers.

Hierarchy

```

IAgilentU2701A
  |
  | Trigger
  |   |
  |   | TV
  |   |   |
  |   |   | SignalFormat
  
```

Return Format

Item	Type	Description
AgilentU2701ATV SignalFormat Enum	Enum	See “ AgilentU2701ATVSignalFormatEnum ” on page 94 for more information.

Example

```
Sub Main()  
    ' Create an instance of the driver  
    Dim Driver As New AgilentU2701A  
    ' SignalFormat Statement  
    ' To Get SignalFormat from the Instrument  
    Dim SignalFormat As AgilentU2701ATVSignalFormatEnum  
    SignalFormat = Driver.Trigger.TV.SignalFormat  
    ' To Set SignalFormat eg. NTSC  
    Driver.Trigger.TV.SignalFormat =  
        AgilentU2701ATVSignalFormatEnum.AgilentU2701ATVSignalFormatN  
        TSC  
End Sub
```

Type

Type

Property

Function

Get and Set

Description

This command returns/sets the kind of event that triggers the oscilloscope.

Hierarchy

```
IAgilentU2701A
  └ Trigger
    └ TV
      └ Type
```

Return Format

Item	Type	Description
AgilentU2701A TriggerTypeEnum	Enum	See “AgilentU2701ATriggerTypeEnum” on page 93 for more information.

Example

```
Sub Main()
    ' Create an instance of the driver
    Dim Driver As New AgilentU2701A
    ' Type Statement
    ' To Get Type from the Instrument
    Dim Type As AgilentU2701ATriggerTypeEnum
    Type = Driver.Trigger.Type
    ' To Set Type eg. Edge
    Driver.Trigger.Type =
        AgilentU2701ATriggerTypeEnum.AgilentU2701ATriggerEdge
End Sub
```

Width

This interface configures condition, polarity, and threshold level of width trigger.

Condition

Type

Property

Function

Get and Set

Description

This command returns/sets whether a pulse within or outside the high and low thresholds triggers the oscilloscope.

Hierarchy

```
IAgilentU2701A
├── Trigger
│   ├── Width
│   └── Condition
```

Return Format

Item	Type	Description
AgilentU2701A WidthCondition Enum	Enum	See " AgilentU2701AWidthConditionEnum " on page 97 for more information.

Example

```
Sub Main()  
    ' Create an instance of the driver  
    Dim Driver As New AgilentU2701A  
    ' Condition Statement  
    ' To Get Condition from the Instrument  
    Dim Condition As AgilentU2701AWidthConditionEnum  
    Condition = Driver.Trigger.Width.condition  
    ' To Set Condition eg. Outside  
    Driver.Trigger.Width.condition =  
        AgilentU2701AWidthConditionEnum.AgilentU2701AWidthConditionO  
        utside  
End Sub
```

Configure

Type

Method

Function

Set

Description

This command configures the width trigger *Source*, *Level*, *ThresholdLow*, *ThresholdHigh*, *Polarity*, and *Condition*. A width trigger occurs when a pulse, which passes through *Level*, with a width between or outside, the width threshold is detected.

Hierarchy

```
IAgilentU2701A
├ Trigger
│   └ Width
│       └ Configure(Source, Level, ThresholdLow, ThresholdHigh,
                    Polarity, Condition)
```

Parameters

Item	Type	Description
Source	String	Specifies the trigger source. This value sets the <code>Trigger.Source</code> property.
Level	Double	Specifies the trigger level. This value sets the <code>Trigger.Level</code> property.
ThresholdLow	Double	Sets the width triggering low threshold in seconds. This value sets the <code>Width.ThresholdLow</code> property.
ThresholdHigh	Double	Sets the width triggering high threshold in seconds. This value sets the <code>Width.ThresholdHigh</code> property.
Polarity	AgilentU2701AWidthPolarityEnum	Specifies the width polarity. This value sets the <code>Width.Polarity</code> property. See “AgilentU2701AWidthPolarityEnum” on page 97 for more information.
Condition	AgilentU2701AWidthConditionEnum	Specifies the width condition. This value sets the <code>Width.Condition</code> property. See “AgilentU2701AWidthConditionEnum” on page 97 for more information.

Example

```
Sub Main()
    ' Create an instance of the driver
    Dim Driver As New AgilentU2701A
    ' Configure Statement
    Driver.Trigger.Width.Configure("Channel1", 0, 0, 0.000000016,
        AgilentU2701AWidthPolarityEnum.AgilentU2701AWidthPolarityPositive,
        AgilentU2701AWidthConditionEnum.AgilentU2701AWidthConditionOutside)
End Sub
```

Polarity

Type

Property

Function

Get and Set

Description

This command returns/sets the polarity of the pulse that triggers the oscilloscope.

Hierarchy

```
IAgilentU2701A
  |
  | L Trigger
  |   |
  |   | L Width
  |   |   |
  |   |   | L Polarity
```

Return Format

Item	Type	Description
AgilentU2701A WidthPolarity Enum	Enum	See “AgilentU2701AWidthPolarityEnum” on page 97 for more information.

Example

```
Sub Main()  
    ' Create an instance of the driver  
    Dim Driver As New AgilentU2701A  
    ' Polarity Statement  
    ' To Get Polarity from the Instrument  
    Dim Polarity As AgilentU2701AWidthPolarityEnum  
    Polarity = Driver.Trigger.Width.polarity  
    ' To Set Polarity eg. Positive  
    Driver.Trigger.Width.polarity =  
        AgilentU2701AWidthPolarityEnum.AgilentU2701AWidthPolarityPos  
        itive  
End Sub
```

ThresholdHigh

Type

Property

Function

Get and Set

Description

This command returns/sets the high width threshold time, expressed in seconds.

Hierarchy

```
IAgilentU2701A
├── Trigger
│   └── Width
│       └── ThresholdHigh
```

Return Format

Double

Example

```
Sub Main()
    ' Create an instance of the driver
    Dim Driver As New AgilentU2701A
    ' ThresholdHigh Statement
    ' To Get ThresholdHigh from the Instrument
    Dim ThresholdHigh As Double
    ThresholdHigh = Driver.Trigger.Width.ThresholdHigh
    ' To Set ThresholdHigh eg. 0.000000016
    Driver.Trigger.Width.ThresholdHigh = 0.000000016
End Sub
```

ThresholdLow

Type

Property

Function

Get and Set

Description

This command returns/sets the low width threshold time, expressed in seconds.

Hierarchy

```
IAgilentU2701A
├── Trigger
│   ├── Width
│   │   └── ThresholdLow
```

Return Format

Double

Example

```
Sub Main()
    ' Create an instance of the driver
    Dim Driver As New AgilentU2701A
    ' ThresholdLow Statement
    ' To Get ThresholdLow from the Instrument
    Dim ThresholdLow As Double
    ThresholdLow = Driver.Trigger.Width.ThresholdLow
    ' To Set ThresholdLow eg. 0
    Driver.Trigger.Width.ThresholdLow = 0
End Sub
```

Clear

Type

Method

Function

Set

Description

This command clears all event registers and error queues. The enable registers are unaffected.

Hierarchy

```
IAgilentU2701A
├── Status
│   └── Clear()
```

Example

```
Sub Main()
    ' Create an instance of the driver
    Dim Driver As New AgilentU2701A
    ' Clear Statement
    Driver.Status.Clear()
End Sub
```

ConfigureServiceRequest

Type

Method

Function

Set

Description

This command clears all the enable registers. It then sets the appropriate transition filters and enable registers so when the specified event(s) occur(s) the instrument requests service. All other events are disabled from generating a service request. To detect a service request the client application must poll the status byte using the [SerialPoll](#) method or [Register](#) property and test the request service bit.

Hierarchy

```
IAgilentU2701A
├── Status
│   └── ConfigureServiceRequest(Reason)
```

Parameters

Item	Type	Description
Reason	AgilentU2701A SRQReasonEnum	The defined values are expressed in the powers of two: 1, 2, 4, and so on. You can OR several reasons together so multiple events can generate a service request. See “AgilentU2701ASRQReasonEnum” on page 87 for more information.

2 Configuration

Example

```
Sub Main()  
    ' Create an instance of the driver  
    Dim Driver As New AgilentU2701A  
    ' ConfigureServiceRequest Statement  
    Driver.Status.ConfigureServiceRequest (AgilentU2701ASRQReasonE  
        num.AgilentU2701ASRQReasonEsrCommandError)  
End Sub
```

Preset

Type

Method

Function

Set

Description

This command sets the SCPI defined enable registers and transition filters.

Hierarchy

```
IAgilentU2701A
├── Status
│   └── Preset()
```

Example

```
Sub Main()
    ' Create an instance of the driver
    Dim Driver As New AgilentU2701A
    ' Preset Statement
    Driver.Status.Preset()
End Sub
```

Register

Type

Property

Function

Get and Set

Description

This command returns/sets the instrument status registers.

Hierarchy

```
IAgilentU2701A
├── Status
│   └── Register(Register, SubRegister, val)
```

Parameters

Item	Type	Description
Register	AgilentU2701A StatusRegister Enum	The status register to access. See “AgilentU2701AStatusRegisterEnum” on page 89 for available registers.
SubRegister	AgilentU2701A StatusSubRegister Enum	The status sub register to access. See “AgilentU2701AStatusSubRegisterEnum” on page 90 for available sub registers.
val	Long/Int32	Instrument Status Register value

Return Format

Item	Type	Description
val	Long/Int32	Instrument Status Register value

Example

```

Sub Main()
    ' Create an instance of the driver
    Dim Driver As New AgilentU2701A
    ' Register Statement
    ' To Get Register from Instrument
    Dim val As Int32
    val =
        Driver.Status.Register(AgilentU2701AStatusRegisterEnum.AgilentU2701AStatusRegisterArmEvent,
            AgilentU2701AStatusSubRegisterEnum.AgilentU2701AStatusSubRegisterCondition)
    ' To Set Register eg. 0
    Driver.Status.Register(AgilentU2701AStatusRegisterEnum.AgilentU2701AStatusRegisterArmEvent,
        AgilentU2701AStatusSubRegisterEnum.AgilentU2701AStatusSubRegisterCondition) = 0
End Sub

```

SerialPoll

Type

Property

Function

Get

Description

This command returns the serial poll of the instrument status byte.

Hierarchy

```
IAgilentU2701A
├── Status
│   └── SerialPoll
```

Return Format

Long/Int32

Example

```
Sub Main()
    ' Create an instance of the driver
    Dim Driver As New AgilentU2701A
    ' SerialPoll Statement
    Dim SerialPoll As Int32
    SerialPoll = Driver.Status.SerialPoll
End Sub
```

TimeoutMilliseconds

Type

Property

Function

Set

Description

This command sets the value, in milliseconds, of the default timeout used by I/O operations. This property provides access to the driver Visa Session Timeout. Only in rare, unusual circumstances should you set this property. Driver methods and properties with operations which take a significant time to perform are responsible for adjusting the I/O timeout to an appropriate value. Some methods provide a *MaxTimeMilliseconds* parameter which gives you direct control over the timeout value for that method. Sometimes, however, increasing the timeout value can work around an obscure driver defect.

Hierarchy

```
IAgilentU2701A
├ System
└ TimeoutMilliseconds
```

Return Format

Long/Int32

2 Configuration

Example

```
Sub Main()  
    ' Create an instance of the driver  
    Dim Driver As New AgilentU2701A  
    ' TimeoutMilliseconds Statement  
    ' To Get TimeoutMilliseconds from the Instrument  
    Dim TimeoutMilliseconds As Int32  
    TimeoutMilliseconds = Driver.System.TimeoutMilliseconds  
    ' To Set TimeoutMilliseconds eg. 5000  
    Driver.System.TimeoutMilliseconds = 5000  
End Sub
```

WaitForOperationComplete

Type

Method

Function

Set

Description

This command sets the instrument not to return until previously started operations are completed or the *MaxTimeMilliseconds* time have expired.

Hierarchy

```
IAgilentU2701A
  | System
    | WaitForOperationComplete (MaxTimeMilliseconds)
```

Return Format

String/BTSR

Example

```
Sub Main()
    ' Create an instance of the driver
    Dim Driver As New AgilentU2701A
    ' WaitForOperationComplete Statement
    Driver.System.WaitForOperationComplete(50000)
End Sub
```

Disable

Type

Method

Function

Set

Description

This command quickly places the instrument in a state where it has no, or minimal, effect on the external system to which it is connected. This state is not necessarily a known state.

Hierarchy

```
IAgilentU2701A
├── Utility
│   └── Disable()
```

Example

```
Sub Main()
    ' Create an instance of the driver
    Dim Driver As New AgilentU2701A
    ' Disable Statement
    Driver.Utility.Disable()
End Sub
```

ErrorQuery

Type

Method

Function

Get

Description

This command queries the instrument and returns the instrument specific error information. This function can be used when [QueryInstrumentStatus](#) is `True` to retrieve error details when the driver detects an instrument error.

Hierarchy

```
IAgilentU2701A
├── Utility
│   └── ErrorQuery(ErrorCode, ErrorMessage)
```

Return Format

Item	Type	Description
ErrorCode	Long/Int32	Instrument error code.
ErrorMessage	String/BSTR	Instrument error message.

Example

```
Sub Main()
    ' Create an instance of the driver
    Dim Driver As New AgilentU2701A
    ' ErrorQuery Statement
    Dim ErrorCode As Int32 = 0
    Dim ErrorMessage As String = ""
    Driver.Utility.ErrorQuery(ErrorCode, ErrorMessage)
End Sub
```

LockObject

Type

Method

Function

Set

Description

Obtains a multithread lock on the driver after waiting until all other execution threads have released their locks on the instrument session.

Hierarchy

```
IAgilentU2701A
├── Utility
│   └── LockObject()
```

Example

```
Sub Main()
    ' Create an instance of the driver
    Dim Driver As New AgilentU2701A
    ' LockObject Statement
    Driver.Utility.LockObject()
End Sub
```


Reset

Type

Method

Function

Set

Description

This command places the instrument in a known state and configures instrument options on which the IVI specific driver depends (for example, enabling/disabling headers). For an IEEE-488.2 instrument, Reset sends the command string *RST to the instrument.

Hierarchy

```
IAgilentU2701A
├── Utility
│   └── Reset()
```

Example

```
Sub Main()
    ' Create an instance of the driver
    Dim Driver As New AgilentU2701A
    ' Reset Statement
    Driver.Utility.Reset()
End Sub
```

ResetWithDefaults

Type

Method

Function

Set

Description

This command does the equivalent of [Reset](#) and then, disables class extension capability groups, sets attributes to initial values defined by class specs, and configures the driver to option string settings used when [Initialize](#) was last executed.

Hierarchy

```
IAgilentU2701A
├── Utility
│   └── ResetWithDefaults()
```

Example

```
Sub Main()
    ' Create an instance of the driver
    Dim Driver As New AgilentU2701A
    ' ResetWithDefaults Statement
    Driver.Utility.ResetWithDefaults()
End Sub
```

SelfTest

Type

Method

Function

Get

Description

This command performs an instrument self-test, waits for the instrument to complete the test, and queries the instrument for the results. If the instrument passes the test, *TestResult* is “0” and *TestMessage* is “Self test passed”.

Hierarchy

```

IAgilentU2701A
├── Utility
│   └── SelfTest(TestResult, TestMessage)

```

Return Format

Item	Type	Description
TestResult	Long/Int32	Numeric result from the self-test operation. 0 = no error (test passed).
TestMessage	String/BSTR	Self-test status message.

2 Configuration

Example

```
Sub Main()  
    ' Create an instance of the driver  
    Dim Driver As New AgilentU2701A  
    ' SelfTest Statement  
    Dim TestResult As Int32 = 0  
    Dim TestMessage As String = ""  
    Driver.Utility.SelfTest(TestResult, TestMessage)  
End Sub
```

UnlockObject

Type

Method

Function

Set

Description

This command releases a previously obtained multithread lock.

Hierarchy

```
IAgilentU2701A
├ Utility
│   └ UnlockObject()
```

Example

```
Sub Main()
    ' Create an instance of the driver
    Dim Driver As New AgilentU2701A
    ' UnlockObject Statement
    Driver.Utility.UnlockObject()
End Sub
```

Enumeration Members

This section describes the members of each enumeration used in this specific IVI-COM driver.

AgilentU2701AGlitchConditionEnum

Description

IVI scope class-compliant values for glitch trigger condition.

Members

Member name	Value	Description
AgilentU2701A GlitchCondition LessThan	1	The oscilloscope triggers when the pulse width is less than the value you specify with the Glitch.Width property.
AgilentU2701A GlitchCondition GreaterThan	2	The oscilloscope triggers when the pulse width is greater than the value you specify with the Glitch.Width property.

AgilentU2701AGlitchPolarityEnum

Description

IVI scope class-compliant values for glitch trigger polarity.

Members

Member name	Value	Description
AgilentU2701A GlitchPolarity Positive	1	The oscilloscope triggers on a positive glitch.
AgilentU2701A GlitchPolarity Negative	2	The oscilloscope triggers on a negative glitch.

AgilentU2701ASRQReasonEnum

Description

Enumeration for the *Reason* parameter of the [ConfigureServiceRequest](#) method.

Members

Member name	Value	Description
AgilentU2701A SRQReasonStb MAV	1	Message Available. Bit 4 in the status byte.
AgilentU2701A SRQReasonStb Msg	2	Error/Event Queue Message Available. Bit 2 in the status byte. The Error/Event queue may be read by the ErrorQuery method.
AgilentU2701A SRQReasonEsr OPC	4	Operation Complete. Bit 0 of the standard event status register.

2 Configuration

Member name	Value	Description
AgilentU2701A SRQReasonEsr QueryError	8	Query Error. Bit 2 of the standard event status register.
AgilentU2701A SRQReasonEsr DeviceError	16	Device Dependent Error. Bit 3 of the standard event status register.
AgilentU2701A SRQReasonEsr ExecutionError	32	Execution Error. Bit 4 of the standard event status register.
AgilentU2701A SRQReasonEsr CommandError	64	Command Error. Bit 5 of the standard event status register.
AgilentU2701A SRQReasonEsr UserRequest	128	User Request. Bit 6 of the standard event status register.
AgilentU2701A SRQReasonEsr PowerOn	256	Power On. Bit 7 of the standard event status register.
AgilentU2701A SRQReasonStbTrg	512	Trigger Event has occurred. Bit 0 in the status byte register.
AgilentU2701A SRQReasonStb User	1024	User Event has occurred. Bit 1 in the status byte register.

AgilentU2701AStatusRegisterEnum

Description

Enumeration for the *Register* parameter of the [Register](#) property.

Members

Member name	Value	Description
AgilentU2701A StatusRegister StatusByte	0	Status Byte register. Conditions defined by IEEE 488.2.
AgilentU2701A StatusRegister StandardEvent	1	Standard Event Status register. Conditions defined by IEEE 488.2.
AgilentU2701A StatusRegister Operation	2	Operation. Conditions which are part of the instrument's normal operation.
AgilentU2701A StatusRegister OverloadEvent	3	The Overload Status Register captures overload events and probe faults that occur on the input channels. This register does not support the Conditions subregister.
AgilentU2701A StatusRegister TriggerEvent	4	The Trigger Event Register captures the trigger event. This register does not support the Conditions or Enable subregisters.
AgilentU2701A StatusRegister ArmEvent	5	The Armed Event Register captures the arm event. An arm event occurs when the oscilloscope has fulfilled all its pre-trigger requirements and is waiting for a trigger event. This register does not support the Conditions or Enable subregisters.

AgilentU2701AStatusSubRegisterEnum

Description

Enumeration for the *SubRegister* parameter of the Register property in the Status interface.

Members

Member name	Value	Description
AgilentU2701A StatusSubRegister Condition	0	Conditions Register. Read only and not available with the Standard Event Status register. Condition bits represent the current instrument state. Reading a condition register does not change the value of the bits.
AgilentU2701A StatusSubRegister Event	3	Event Register. Read only and not available with the Status Byte register. Event bits capture changes in condition bits. Reading an event register clears it.
AgilentU2701A StatusSubRegister Enable	4	Enable Register. Can be read or written and is available for all registers. Enable bits select whether an event bit causes a register summary bit, a kind of condition bit, to become True. Thus, an event can propagated to the status byte and finally to request service. Though the bits in the status byte are not technically event bits, the status byte enable register selects which bits in the status byte cause a service request.

AgilentU2701ATriggerCouplingEnum

Description

IVI Scope class-compliant values for trigger Coupling.

Members

Member name	Value	Description
AgilentU2701A TriggerCouplingAC	1	The oscilloscope AC couples the trigger signal.
AgilentU2701A TriggerCouplingDC	2	The oscilloscope DC couples the trigger signal.
AgilentU2701A TriggerCouplingLF Reject	3	The oscilloscope filters out the low frequencies from the trigger signal.
AgilentU2701A TriggerCouplingHF Reject	4	The oscilloscope filters out the high frequencies from the trigger signal.

AgilentU2701ATriggerModifierEnum

Description

IVI Scope class-compliant values for trigger Modifier.

Members

Member name	Value	Description
AgilentU2701A TriggerModifier None	1	The oscilloscope waits until the trigger the end-user specifies occurs.
AgilentU2701A TriggerModifier Auto	2	The oscilloscope automatically triggers if the configured trigger does not occur within the oscilloscope's timeout period.

AgilentU2701ATriggerSlopeEnum

Description

IVI Scope class-compliant values for edge trigger Slope.

Members

Member name	Value	Description
AgilentU2701A TriggerSlope Negative	0	Triggers will occur on the falling edge.
AgilentU2701A TriggerSlope Positive	1	Triggers will occur on the rising edge.
AgilentU2701A TriggerSlopeEither	2	Triggers will occur on either the rising or falling edge.
AgilentU2701A TriggerSlope Alternate	3	Triggers will occur alternately on the rising and falling edges.

AgilentU2701ATriggerTypeEnum

Description

IVI Scope class-compliant values for trigger Type.

Members

Member name	Value	Description
AgilentU2701A TriggerEdge	1	Configures the oscilloscope for edge triggering. An edge trigger occurs when the trigger signal specified with the Trigger.Source property passes the voltage threshold specified with the Trigger.Level property and has the slope specified with the Trigger.Slope property.
AgilentU2701A TriggerGlitch	2	Configures the oscilloscope for glitch triggering. Use the IviScopeGlitchTrigger extension properties and methods to configure the trigger.
AgilentU2701A TriggerTV	3	Configures the oscilloscope for triggering on TV signals. Use the IviScopeTVTrigger extension properties and methods to configure the trigger.
AgilentU2701A TriggerWidth	4	Configures the oscilloscope for width triggering. Use the IviScopeWidthTrigger extension properties and methods to configure the trigger.

AgilentU2701ATVSignalFormatEnum

Description

IVI Scope class-compliant values for TV trigger SignalFormat.

Members

Member name	Value	Description
AgilentU2701ATV SignalFormat NTSC	1	Configures the oscilloscope to trigger on the NTSC signal format.
AgilentU2701ATV SignalFormatPAL	2	Configures the oscilloscope to trigger on the PAL signal format.
AgilentU2701ATV SignalFormat SECAM	3	Configures the oscilloscope to trigger on the SECAM signal format.

AgilentU2701ATVTriggerEventEnum

Description

IVI Scope class-compliant values for TV trigger Event.

Members

Member name	Value	Description
AgilentU2701ATV TriggerEventField1	1	Sets the oscilloscope to trigger on field 1 of the video signal.
AgilentU2701ATV TriggerEventField2	2	Sets the oscilloscope to trigger on field 2 of the video signal.
AgilentU2701ATV TriggerEventAny Field	3	Sets the oscilloscope to trigger on any field.
AgilentU2701ATV TriggerEventAny Line	4	Sets the oscilloscope to trigger on any line.
AgilentU2701ATV TriggerEventField1 LineNumber	5	Sets the oscilloscope to trigger on a specific line number in Field 1 you specify with the TV.LineNumber property.
AgilentU2701ATV TriggerEventField2 LineNumber	6	Sets the oscilloscope to trigger on a specific line number in Field 2 you specify with the TV.LineNumber property.

AgilentU2701AVerticalCouplingEnum

Description

IVI Scope class-compliant values for channel Coupling.

Members

Member name	Value	Description
AgilentU2701A VerticalCoupling AC	0	The oscilloscope AC couples the input signal.
AgilentU2701A VerticalCoupling DC	1	The oscilloscope DC couples the input signal.
AgilentU2701A VerticalCoupling LFReject	2	The oscilloscope rejects low frequency.
AgilentU2701A VerticalCoupling HFReject	3	The oscilloscope rejects high frequency.

AgilentU2701AWidthConditionEnum

Description

IAgilentU2701A instrument-specific values for the polarity of the pulse that triggers the oscilloscope.

Members

Member name	Value	Description
AgilentU2701A WidthPolarity Positive	1	Configures the oscilloscope to trigger on positive pulses that have a width that meets the condition the user specifies with the Width.Condition property.
AgilentU2701A WidthPolarity Negative	2	Configures the oscilloscope to trigger on negative pulses that have a width that meets the condition the user specifies with the Width.Condition property.

AgilentU2701AWidthPolarityEnum

Description

IAgilentU2701A instrument-specific values for the polarity of the pulse that triggers the oscilloscope.

Members

Member name	Value	Description
AgilentU2701A WidthPolarity Positive	1	Configures the oscilloscope to trigger on positive pulses that have a width that meets the condition the user specifies with the Width.Condition property.
AgilentU2701A WidthPolarity Negative	2	Configures the oscilloscope to trigger on negative pulses that have a width that meets the condition the user specifies with the Width.Condition property.

2 Configuration



3 Acquisition

ConfigureRecord	100
Interpolation	102
NumberOfAverages	104
RecordLength	105
SampleMode	106
SampleRate	107
StartTime	108
TimePerRecord	109
Type	112
Enumeration Members	114

This chapter describes the acquisition commands used to program the U2701A/U2702A USB modular oscilloscopes over the remote interface. You can use the commands in this chapter to configure the acquisition type, the size of the waveform record, the length of time that corresponds to overall waveform record, and the position of the first point in the waveform record relative to the trigger event.



ConfigureRecord

Type

Method

Function

Set

Description

This command configures the most commonly used properties of the oscilloscope channel sub-system. Use this command to enable or disable the channel and to set the range, offset, coupling, and probe attenuation values.

Hierarchy

```
IAgilentU2701A
├─ Acquisition
│   └─ ConfigureRecord(TimePerRecord, AcquisitionStartTime)
```

Parameters

Item	Type	Description
TimePerRecord	Double	Specifies the time per record. This value sets the Horizontal TimePerRecord property.
AcquisitionStart Time	Double	Specifies the position of the first point in the waveform record relative to the trigger event. This value sets the Acquisition. StartTime property.

Example

```
Sub Main()  
    ' Create an instance of the driver  
    Dim Driver As New AgilentU2701A  
    ' ConfigureRecord Statement  
    Driver.Acquisition.ConfigureRecord(0.001, 0.0)  
End Sub
```

Interpolation

Type

Property

Function

Get and Set

Description

This command returns/sets the interpolation method the oscilloscope uses when it cannot sample a voltage for every point in the waveform record.

Hierarchy

```
IAgilentU2701A
├─ Acquisition
│   └─ Interpolation
```

Return Format

Item	Type	Description
AgilentU2701A InterpolationEnum	Enum	See " AgilentU2701AInterpolationEnum " on page 116.

Example

```
Sub Main()  
    ' Create an instance of the driver  
    Dim Driver As New AgilentU2701A  
    ' Interpolation Statement  
    ' To Get Interpolation from Instrument  
    Dim Interpolation As New AgilentU2701AInterpolationEnum  
    Interpolation = Driver.Acquisition.Interpolation  
    ' To Set Interpolation eg. SineX  
    Driver.Acquisition.Interpolation =  
        AgilentU2701AInterpolationEnum.AgilentU2701AInterpolationSin  
        eX  
End Sub
```

NumberOfAverages

Type

Property

Function

Get and Set

Description

This command returns/sets the number of waveforms the oscilloscope acquires and averages before returning to idle state.

Hierarchy

```
IAgilentU2701A
├ Acquisition
│   └ NumberOfAverages
```

Return Format

Long/Int32

Example

```
Sub Main()
    ' Create an instance of the driver
    Dim Driver As New AgilentU2701A
    ' NumberOfAverage Statement
    ' To Get Number of Average from Instrument
    Dim NumberOfAverage As Int32
    NumberOfAverage = Driver.Acquisition.NumberOfAverages
    ' To Set Number of Average eg. 30
    Driver.Acquisition.NumberOfAverages = 30
End Sub
```


RecordLength

Type

Property

Function

Get

Description

This command returns the actual number of points the oscilloscope acquires for each channel. It is equal to or greater than the minimum number of points specified with the `IviScopeAcquisition.NumberOfPointsMin` command.

Hierarchy

```
IAgilentU2701A
├─ Acquisition
│   └─ RecordLength
```

Return Format

Long/Int32

Example

```
Sub Main()
    ' Create an instance of the driver
    Dim Driver As New AgilentU2701A
    ' RecordLength Statement
    Dim RecordLength As Long
    RecordLength = Driver.Acquisition.RecordLength
End Sub
```

SampleMode

Type

Property

Function

Get

Description

This command returns the sample mode that the oscilloscope is currently using.

Hierarchy

```
IAgilentU2701A
├─ Acquisition
│   └─ SampleMode
```

Return Format

Item	Type	Description
AgilentU2701A SampleMode Enum	Enum	See “ AgilentU2701ASampleModeEnum ” on page 116.

Example

```
Sub Main()
    ' Create an instance of the driver
    Dim Driver As New AgilentU2701A
    ' SampleMode Statement
    Dim SampleMode As AgilentU2701ASampleModeEnum
    SampleMode = Driver.Acquisition.SampleMode
End Sub
```

SampleRate

Type

Property

Function

Get

Description

This command returns the effective digitizing rate using the current configuration. The units are expressed in samples per second.

Hierarchy

```
IAgilentU2701A
├─ Acquisition
│   └─ SampleRate
```

Return Format

Double

Example

```
Sub Main()
    ' Create an instance of the driver
    Dim Driver As New AgilentU2701A
    ' SampleRate Statement
    Dim SampleRate As Double
    SampleRate = Driver.Acquisition.SampleRate
End Sub
```

StartTime

Type

Property

Function

Get and Set

Description

This command returns/sets the length of time from the trigger event to the first point in the waveform record. The units are expressed in seconds. If positive, the first point in the waveform occurs after the trigger. If negative, the first point in the waveform occurs before the trigger.

Hierarchy

```
IAgilentU2701A
├─ Acquisition
│   └─ StartTime
```

Return Format

Double

Example

```
Sub Main()
    ' Create an instance of the driver
    Dim Driver As New AgilentU2701A
    ' StartTime Statement
    ' To Get Start Time from the Instrument
    Dim StartTime As Double
    StartTime = Driver.Acquisition.StartTime
    ' To Set Start Time eg. 0.0 s
    Driver.Acquisition.StartTime = 0.0
End Sub
```

TimePerRecord

Type

Property

Function

Get and Set

Description

This command returns/sets the time in seconds that corresponds to the record length.

Hierarchy

```
IAgilentU2701A
├─ Acquisition
│   └─ TimePerRecord
```

Return Format

Double

Remarks

The time per record length is equivalent to the Time/Div multiplied by 10 at the scope setting. The Maximum data point per second you can achieve is 1250, except when in interleave mode (only available with the Agilent Measurement Manager), you can achieve 2000 data points.

Time/Div	TimePer Record	Maximum Data Point
1 ns	10 ns	5
2 ns	20 ns	10
5 ns	50 ns	25
10 ns	100 ns	50
20 ns	200 ns	100
50 ns	500 ns	250
100 ns	1 μ s	500
200 ns	2 μ s	100
500 ns	5 μ s	1250
1 μ s	10 μ s	1250
2 μ s	20 μ s	1250
5 μ s	50 μ s	1250
10 μ s	100 μ s	1250
20 μ s	200 μ s	1250
50 μ s	500 μ s	1250
100 μ s	1 ms	1250
200 μ s	2 ms	1250
500 μ s	5 ms	1250

Time/Div	TimePer Record	Maximum Data Point
1 ms	10 ms	1250
2 ms	20 ms	1250
5 ms	50 ms	1250
10 ms	100 ms	1250
20 ms	200 ms	1250
50 ms	500 ms	1250
100 ms	1 s	1250
200 ms	2 s	1250
500 ms	5 s	1250
1 s	10 s	1250
2 s	20 s	1250
5 s	50 s	1250
10 s	100 s	1250
20 s	200 s	1250
50 s	500 s	1250

Example

```
Sub Main()  
    ' Create an instance of the driver  
    Dim Driver As New AgilentU2701A  
    ' TimePerRecord Statement  
    ' To Get Time Per Record from the Instrument  
    Dim TimePerRecord As Double  
    TimePerRecord = Driver.Acquisition.TimePerRecord  
    ' To Set Time Per Record eg. 0.001  
    Driver.Acquisition.TimePerRecord = 0.001  
End Sub
```

Type

Type

Property

Function

Get and Set

Description

This commands returns/sets how the oscilloscope acquires data and fills the waveform record. When set to `Envelope` or `Peak Detect`, the oscilloscope acquires minimum and maximum waveforms.

Hierarchy

```
IAgilentU2701A
  | Acquisition
  |   | Type
```

Return Format

Item	Type	Description
AgilentU2701A AcquisitionType Enum	Enum	See " AgilentU2701AAcquisitionTypeEnum " on page 115.

Example

```
Sub Main()  
    ' Create an instance of the driver  
    Dim Driver As New AgilentU2701A  
    ' Type Statement  
    ' To Get Type from the Instrument  
    Dim Type As AgilentU2701AAcquisitionTypeEnum  
    Type = Driver.Acquisition.Type  
    ' To Set Type eg. Normal  
    Driver.Acquisition.Type =  
        AgilentU2701AAcquisitionTypeEnum.AgilentU2701AAcquisitionTyp  
        eNormal  
End Sub
```

Enumeration Members

This section describes the members of each enumeration used in this specific IVI-COM driver.

AgilentU2701AAcquisitionStatusEnum

Description

IVI scope class-compliant values for the *Status* parameter of the acquisition status method.

Members

Member name	Value	Description
AgilentU2701A AcqInProgress	0	The oscilloscope is still acquiring data.
AgilentU2701A AcqComplete	1	The oscilloscope has completed the acquisition.
AgilentU2701A AcqStatus Unknown	-1	The oscilloscope cannot determine the status of the acquisition.

AgilentU2701AAcquisitionTypeEnum

Description

IVI scope class-compliant values for acquisition type.

Members

Member name	Value	Description
AgilentU2701A AcquisitionType Normal	0	Configures the oscilloscope to acquire one sample for each point in the waveform record. The oscilloscope uses real-time or equivalent time sampling.
AgilentU2701A AcquisitionType PeakDetect	1	Sets the oscilloscope to the peak-detect acquisition mode. The oscilloscope oversamples the input signal and keeps the minimum and maximum values that correspond to each position in the waveform record. The oscilloscope uses only real-time sampling.
AgilentU2701A AcquisitionType Average	2	Configures the oscilloscope to acquire multiple waveforms and calculates the average value for each point in the waveform record. The end-user specifies the number of waveforms to acquire with the NumberOfAverages property. The oscilloscope uses real-time or equivalent time sampling.

AgilentU2701AInterpolationEnum

Description

IVI scope class-compliant values for acquisition interpolation.

Members

Member name	Value	Description
AgilentU2701A InterpolationNone	1	The oscilloscope does not interpolate points in the waveform. Instead, the driver sets every element in the waveform record for which the oscilloscope cannot receive a value to an IEEE-defined NaN (Not-a-Number) value. Use the IsWaveformElementInvalid method to determine if the waveform record element is invalid.
AgilentU2701A InterpolationSineX	2	The oscilloscope uses a $\sin(x)/x$ calculation to interpolate a value when it cannot resolve a voltage in the waveform record.

AgilentU2701ASampleModeEnum

Description

IVI Scope class-compliant values for acquisition [SampleMode](#).

Members

Member name	Value	Description
AgilentU2701A SampleModeReal Time	0	Indicates that the oscilloscope is using real-time sampling.



4 Waveform Display

Abort	118
AutoSetup	119
Count	120
Initiate	121
IsWaveformElementInvalid	122
Item	124

This chapter describes the waveform display commands used to program the U2701A/U2702A USB modular oscilloscopes over the remote interface. The statements in this section is used to acquire waveform data from the oscilloscope. You can use the commands in this section to initiate, acquire, and abort measurements.



Abort

Type

Method

Function

Set

Description

This command aborts an acquisition and returns the oscilloscope to the Idle state.

Hierarchy

```
IAgilentU2701A
├─ Measurements
│   └─ Abort()
```

Example

```
Sub Main()
    ' Create an instance of the driver
    Dim Driver As New AgilentU2701A
    ' Abort Statement
    Driver.Measurements.Abort()
End Sub
```

AutoSetup

Type

Method

Function

Set

Description

This command automatically configures all the oscilloscopes settings based on the input signals.

Hierarchy

```
IAgilentU2701A
├─ Measurements
│   └─ AutoSetup()
```

Example

```
Sub Main()
    ' Create an instance of the driver
    Dim Driver As New AgilentU2701A
    ' AutoSetup Statement
    Driver.Measurements.AutoSetup()
End Sub
```

Count

Type

Property

Function

Get

Description

This command returns the number of measurements.

Hierarchy

```
IAgilentU2701A
├── Measurements
│   └── Count
```

Return Format

Long/Int32

Example

```
Sub Main()
    ' Create an instance of the driver
    Dim Driver As New AgilentU2701A
    ' Count Statement
    Dim Count As Int32
    Count = Driver.Measurements.Count
End Sub
```


Initiate

Type

Method

Function

Set

Description

This command initiates a waveform acquisition. The oscilloscope leaves the Idle state and waits for a trigger. The oscilloscope acquires a waveform for each enabled channel.

Hierarchy

```
IAgilentU2701A
├─ Measurements
│  └─ Initiate()
```

Example

```
Sub Main()
    ' Create an instance of the driver
    Dim Driver As New AgilentU2701A
    ' Initiate Statement
    Driver.Measurements.Initiate()
End Sub
```

IsWaveformElementInvalid

Type

Method

Function

Get

Description

This command returns `False` if an element in a waveform array returned by the driver contains a valid voltage. This command returns `True` if an element in a waveform array returned by the driver contains a value indicating that the oscilloscope could not sample a voltage.

Hierarchy

```
IAgilentU2701A
├── Measurements
│   └── IsWaveformElementInvalid(Element)
```

Parameters

Item	Type	Description
Element	Double	Pass one of the values from the waveform array returned by the read and fetch waveform methods.

Return Format

Boolean

Example

```
Sub Main()  
    ' Create an instance of the driver  
    Dim Driver As New AgilentU2701A  
    ' IsWaveformElementInvalid Statement  
    Dim Element As Double = 0  
    Dim IsWaveformElementInvalid As Boolean  
    IsWaveformElementInvalid =  
        Driver.Measurements.IsWaveformElementInvalid(Element)  
End Sub
```

Item

This is an interface reference pointer to the IAgilentU2701AMeasurement interface which is selected by the measurement name.

FetchWaveform

Type

Method

Function

Get

Description

This command returns a previously acquired waveform for this channel. The acquisition must be made prior to calling this method. Call this method separately for each channel.

Hierarchy

```
IAgilentU2701A
├── Measurements
│   ├── Item(Name)
│   └── FetchWaveform(WaveformArray, InitialX, XIncrement)
```

Parameters

Item	Type	Description
Name	String	The name of a measurement. This command is used to select the channel the function is to be run on. (For example: Channel 1, Channel 2, and so on.)

Return Format

Item	Type	Description
WaveformArray	Double	The array contains the acquired waveform. Units for the individual array elements are expressed in volts.
InitialX	Double	The time in relation to the trigger event of the first point in the waveform in seconds. Negative values mean that the first point in the waveform array was acquired before the trigger event.
XIncrement	Double	The effective time between points in the acquired waveform in seconds.

Example

```

Sub Main()
    ' Create an instance of the driver
    Dim Driver As New AgilentU2701A
    ' Initialization required
    Driver.Measurements.Initiate()
    ' Get Record Length
    Dim RecordLength As Int32
    RecordLength = Driver.Acquisition.RecordLength
    ' FetchWaveform Statement
    Dim WaveformArray() As Double
    Dim InitialX As Double
    Dim XIncrement As Double
    ReDim WaveformArray(RecordLength - 1)
    Driver.Measurements.Item("Channel1").FetchWaveform(WaveformAr
        ray, InitialX, XIncrement)
End Sub

```

ReadWaveform

Type

Method

Function

Get

Description

This command initiates an acquisition on all enabled channels, waits (up to *MaxTime*) for the acquisition to complete, and returns the waveform for this channel. Call [FetchWaveform](#) to obtain the waveforms for other channels.

Hierarchy

```
IAgilentU2701A
├── Measurements
│   ├── Item(Name)
│       └── ReadWaveform(MaxTimeMilliseconds, WaveformArray,
                        InitialX, XIncrement)
```

Parameters

Item	Type	Description
Name	String	The name of a measurement. This command is used to select the channel the function is to be run on. (For example: Channel 1, Channel 2, and so on.)

Return Format

Item	Type	Description
MaxTime Milliseconds	Long/Int32	Specifies the maximum time the end-user allows for this method to complete in milliseconds.
WaveformArray	Double	The array contains the acquired waveform. Units for the individual array elements are expressed in volts.
InitialX	Double	The time in relation to the trigger event of the first point in the waveform in seconds. Negative values mean that the first point in the waveform array was acquired before the trigger event.
XIncrement	Double	The effective time between points in the acquired waveform in seconds.

Example

```

Sub Main()
    ' Create an instance of the driver
    Dim Driver As New AgilentU2701A
    ' Get Record Length
    Dim RecordLength As Int32
    RecordLength = Driver.Acquisition.RecordLength
    ' ReadWaveform Statement
    Dim WaveformArray() As Double
    Dim InitialX As Double
    Dim XIncrement As Double
    ReDim WaveformArray(RecordLength - 1)
    Driver.Measurements.Item("Channel1").ReadWaveform(50000,
        WaveformArray, InitialX, XIncrement)
End Sub

```

4 Waveform Display



5 Post Analysis

Abort	130
AutoSetup	131
Count	132
Initiate	133
IsWaveformElementInvalid	134
Item	136
MathFunction	146
Name	147
Status	148
Enumeration Members	149

This chapter describes the post analysis commands used to program the U2701A/U2702A USB modular oscilloscopes over the remote interface. The statements in this section is used to analyze the waveform data acquired from the oscilloscope. You can also use the commands in this section to initiate, acquire, and abort measurements.



Abort

Type

Method

Function

Set

Description

This command aborts an acquisition and returns the oscilloscope to the Idle state.

Hierarchy

```
IAgilentU2701A
├─ Measurements
│  └─ Abort()
```

Example

```
Sub Main()
    ' Create an instance of the driver
    Dim Driver As New AgilentU2701A
    ' Abort Statement
    Driver.Measurements.Abort()
End Sub
```

AutoSetup

Type

Method

Function

Set

Description

This command automatically configures all the oscilloscopes settings based on the input signals.

Hierarchy

```
IAgilentU2701A
├─ Measurements
│   └─ AutoSetup()
```

Example

```
Sub Main()
    ' Create an instance of the driver
    Dim Driver As New AgilentU2701A
    ' AutoSetup Statement
    Driver.Measurements.AutoSetup()
End Sub
```

Count

Type

Property

Function

Get

Description

This command returns the number of measurements.

Hierarchy

```
IAgilentU2701A
├── Measurements
│   └── Count
```

Return Format

Long/Int32

Example

```
Sub Main()
    ' Create an instance of the driver
    Dim Driver As New AgilentU2701A
    ' Count Statement
    Dim Count As Int32
    Count = Driver.Measurements.Count
End Sub
```

Initiate

Type

Method

Function

Set

Description

This command initiates a waveform acquisition. The oscilloscope leaves the Idle state and waits for a trigger. The oscilloscope acquires a waveform for each enabled channel.

Hierarchy

```
IAgilentU2701A
├── Measurements
│   └── Initiate()
```

Example

```
Sub Main()
    ' Create an instance of the driver
    Dim Driver As New AgilentU2701A
    ' Initiate Statement
    Driver.Measurements.Initiate()
End Sub
```

IsWaveformElementInvalid

Type

Method

Function

Get

Description

This command returns `False` if an element in a waveform array returned by the driver contains a valid voltage. This command returns `True` if an element in a waveform array returned by the driver contains a value indicating that the oscilloscope could not sample a voltage.

Hierarchy

```
IAgilentU2701A
├── Measurements
│   └── IsWaveformElementInvalid(Element)
```

Parameters

Item	Type	Description
Element	Double	Pass one of the values from the waveform array returned by the read and fetch waveform methods.

Return Format

Boolean

Example

```
Sub Main()  
    ' Create an instance of the driver  
    Dim Driver As New AgilentU2701A  
    ' IsWaveformElementInvalid Statement  
    Dim Element As Double = 0  
    Dim IsWaveformElementInvalid As Boolean  
    IsWaveformElementInvalid =  
        Driver.Measurements.IsWaveformElementInvalid(Element)  
End Sub
```

Item

This is an interface reference pointer to the IAgilentU2701AMeasurement interface which is selected by the measurement name.

FetchWaveform

Type

Method

Function

Get

Description

This command returns a previously acquired waveform for this channel. The acquisition must be made prior to calling this method. Call this method separately for each channel.

Hierarchy

```

IAgilentU2701A
  └─ Measurements
     └─ Item(Name)
        └─ FetchWaveform(WaveformArray, InitialX, XIncrement)

```

Parameters

Item	Type	Description
Name	String	The name of a measurement. This command is used to select the channel the function is to be run on. (For example: Channel 1, Channel 2, and so on.)

Return Format

Item	Type	Description
WaveformArray	Double	The array contains the acquired waveform. Units for the individual array elements are expressed in volts.
InitialX	Double	The time in relation to the trigger event of the first point in the waveform in seconds. Negative values mean that the first point in the waveform array was acquired before the trigger event.
XIncrement	Double	The effective time between points in the acquired waveform in seconds.

Example

```

Sub Main()
    ' Create an instance of the driver
    Dim Driver As New AgilentU2701A
    ' Initialization required
    Driver.Measurements.Initiate()
    ' Get Record Length
    Dim RecordLength As Int32
    RecordLength = Driver.Acquisition.RecordLength
    ' FetchWaveform Statement
    Dim WaveformArray() As Double
    Dim InitialX As Double
    Dim XIncrement As Double
    ReDim WaveformArray(RecordLength - 1)
    Driver.Measurements.Item("Channel1").FetchWaveform(WaveformAr
        ray, InitialX, XIncrement)
End Sub

```

FetchWaveformMeasurement

Type

Method

Function

Get

Description

This command returns a previously acquired waveform measurement for this channel. The acquisition must be made prior to calling this method. Call this method separately for each measurement.

Hierarchy

```
IAgilentU2701A
├── Measurements
│   ├── Item(Name)
│       └── FetchWaveformMeasurement (MeasFunction, Measurement)
```

Parameters

Item	Type	Description
Name	String	The name of a measurement. This command is used to select the channel the function is to be run on. (For example: Channel 1, Channel 2, and so on.)

Return Format

Item	Type	Description
MeasFunction	AgilentU2701A Measurement Enum	Characteristic of the acquired waveform to be measured. See " AgilentU2701AMeasurementEnum " on page 150 for more information.
Measurement	Double	The measured value. The units depend on the measurement that the user specifies with the <i>MeasFunction</i> parameter.

Example

```

Sub Main()
    ' Create an instance of the driver
    Dim Driver As New AgilentU2701A
    ' Initialization required
    Driver.Measurements.Initiate()
    ' FetchWaveformMeasurement Statement
    Dim Measurement As Double
    Driver.Measurements.Item("Channell").FetchWaveformMeasurement
        (AgilentU2701AMeasurementEnum.AgilentU2701AMeasurementFreque
            ncy, Measurement)
End Sub

```

ReadFullWaveform

Type

Method

Function

Get

Description

This command pulls the data directly from the device without data manipulation (interleaving or value conversion). It will automatically detect the 16M/32M data size for each channel.

Hierarchy

```
IAgilentU2701A
  └─ Measurements
     └─ Item(Name)
        └─ ReadFullWaveform(ref Data, ref Length)
```

Parameters

Item	Type	Description
Name	String	The name of a measurement. This command is used to select the channel the function is to be run on. (For example: Channel 1, Channel 2, and so on.)

Return Format

Item	Type	Description
Data	Array	The data that contains a raw waveform data in bytes.
Length	Long/Int32	The length of the data size.

Example

```
Sub Main()  
    ' Create an instance of the driver  
    Dim Driver As New AgilentU2701A  
    ' ReadFullWaveform Statement  
    Dim Data() As Byte  
    Dim Length As Int32  
    Driver.Measurements.Item("Channel1").ReadFullWaveform(Data,  
        Length)  
End Sub
```

ReadWaveform

Type

Method

Function

Get

Description

This command initiates an acquisition on all enabled channels, waits (up to *MaxTime*) for the acquisition to complete, and returns the waveform for this channel. Call [FetchWaveform](#) to obtain the waveforms for other channels.

Hierarchy

```
IAgilentU2701A
├── Measurements
│   ├── Item(Name)
│       └── ReadWaveform(MaxTimeMilliseconds, WaveformArray,
                        InitialX, XIncrement)
```

Parameters

Item	Type	Description
Name	String	The name of a measurement. This command is used to select the channel the function is to be run on. (For example: Channel 1, Channel 2, and so on.)

Return Format

Item	Type	Description
MaxTime Milliseconds	Long/Int32	Specifies the maximum time the end-user allows for this method to complete in milliseconds.
WaveformArray	Double	The array contains the acquired waveform. Units for the individual array elements are expressed in volts.
InitialX	Double	The time in relation to the trigger event of the first point in the waveform in seconds. Negative values mean that the first point in the waveform array was acquired before the trigger event.
XIncrement	Double	The effective time between points in the acquired waveform in seconds.

Example

```

Sub Main()
    ' Create an instance of the driver
    Dim Driver As New AgilentU2701A
    ' Get Record Length
    Dim RecordLength As Int32
    RecordLength = Driver.Acquisition.RecordLength
    ' ReadWaveform Statement
    Dim WaveformArray() As Double
    Dim InitialX As Double
    Dim XIncrement As Double
    ReDim WaveformArray(RecordLength - 1)
    Driver.Measurements.Item("Channel1").ReadWaveform(50000,
        WaveformArray, InitialX, XIncrement)
End Sub

```

ReadWaveformMeasurement

Type

Method

Function

Get

Description

This command returns a previously acquired waveform for this channel. The acquisition must be made prior to calling this method. Call this method separately for each channel.

Hierarchy

```
IAgilentU2701A
├── Measurements
│   └── Item(Name)
│       └── ReadWaveformMeasurement (MeasFunction,
│           MaxTimeMilliseconds, Measurement)
```

Parameters

Item	Type	Description
Name	String	The name of a measurement. This command is used to select the channel the function is to be run on. (For example: Channel 1, Channel 2, and so on.)

Return Format

Item	Type	Description
MeasFunction	AgilentU2701A Measurement Enum	Characteristic of the acquired waveform to be measured. See " AgilentU2701AMeasurementEnum " on page 150 for more information.
MaxTime Milliseconds	Long/Int32	Specifies the maximum time the end-user allows for this method to complete in milliseconds.
Measurement	Double	The measured value. The units depend on the measurement that the user specifies with the <i>MeasFunction</i> parameter.

Example

```

Sub Main()
    ' Create an instance of the driver
    Dim Driver As New AgilentU2701A
    ' Initialization required
    Driver.Measurements.Initiate()
    ' ReadWaveformMeasurement Statement
    Dim Measurement As Double
    Driver.Measurements.Item("Channel1").ReadWaveformMeasurement(
        AgilentU2701AMeasurementEnum.AgilentU2701AMeasurementFrequency, 50000, Measurement)
End Sub

```

MathFunction

Type

Method

Function

Set

Description

This command configures a mathematical operation for Channel 1 and 2. The operation and reverse will be set to “ADD” and “False” by default.

Hierarchy

```
IAgilentU2701A
├─ Measurements
│   └─ MathFunction(Operation, Reverse)
```

Parameters

Item	Type	Description
Operation	AgilentU2701A Measurement Enum	Channel 1 and Channel 2 math operation.
Reverse	Boolean	The operation order of Channel 1 and Channel 2. If True, Channel 2 <operation> Channel 1. If False ,Channel 1 <operation> Channel 2

Example

```
Sub Main()
    ' Create an instance of the driver
    Dim Driver As New AgilentU2701A
    ' MathFunction Statement
    Driver.Measurements.MathFunction(AgilentU2701AMathOperationEnum.AgilentU2701AMathOperationAdd, True)
End Sub
```

Name

Type

Property

Function

Get

Description

This command returns the measurement name for a given index.

Hierarchy

```
IAgilentU2701A
  └─ Measurements
     └─ Name(Index)
```

Parameters

Item	Type	Description
Index	Long/Int32	One based index into the collection of measurements.

Return Format

String/BSTR

Example

```
Sub Main()
    ' Create an instance of the driver
    Dim Driver As New AgilentU2701A
    ' Name Statement
    Dim Name As String
    Name = Driver.Measurements.Name(1)
End Sub
```

Status

Type

Method

Function

Get

Description

This command returns whether an acquisition is in progress, complete, or if the status is unknown.

Hierarchy

```
IAgilentU2701A
  └─ Measurements
     └─ Status()
```

Return Format

Item	Type	Description
AgilentU2701A AcquisitionStatus Enum	Enum	See " AgilentU2701AAcquisitionStatusEnum " on page 114.

Example

```
Sub Main()
    ' Create an instance of the driver
    Dim Driver As New AgilentU2701A
    ' Status Statement
    Driver.Measurements.Status()
End Sub
```

Enumeration Members

This section describes the members of each enumeration used in this specific IVI-COM driver.

AgilentU2701AMathOperationEnum

Description

AgilentU2701A instrument-specific values for channels mathematical operations.

Members

Member name	Value	Description
AgilentU2701A MathOperation Add	0	Add operation between two channels.
AgilentU2701A MathOperation Subtract	1	Subtract operation between two channels.
AgilentU2701A MathOperation Multiply	2	Multiply operation between two channels.
AgilentU2701A MathOperation Divide	3	Divide operation between two channels.

AgilentU2701AMeasurementEnum

Description

IVI scope class-compliant values for the *MeasFunction* parameter read and fetch methods.

Members

Member name	Value	Description
AgilentU2701A MeasurementRise Time	0	The length of time for a rising edge of the signal to rise from the low reference level to the high reference level. The units are expressed in seconds.
AgilentU2701A MeasurementFall Time	1	The length of time for a falling edge of the signal to fall from the high reference level to the low reference level. The units are expressed in seconds.
AgilentU2701A Measurement Frequency	2	The frequency of one complete cycle in the waveform. The units are expressed in hertz.
AgilentU2701A Measurement Period	3	The length of time of one complete cycle in the waveform. The units are expressed in seconds.
AgilentU2701A Measurement VoltageRMS	4	The true Root Mean Square voltage of the entire waveform. The units are expressed in volts.
AgilentU2701A Measurement VoltageRMSAC	5	The true Root Mean Square voltage(AC) of the entire waveform. The units are expressed in volts.
AgilentU2701A Measurement VoltagePeakTo Peak	6	The absolute difference between the Voltage Max and the Voltage Min. The units are expressed in volts.
AgilentU2701A Measurement VoltageMax	7	The maximum amplitude found in the entire waveform. The units are expressed in volts.
AgilentU2701A Measurement VoltageMin	8	The minimum amplitude found in the entire waveform. The units are expressed in volts.

Member name	Value	Description
AgilentU2701A Measurement VoltageHigh	9	The voltage that corresponds to 100% when using the reference levels. The oscilloscope calculates this value using either the min/max or histogram methods. The min/max method uses the maximum value found. The histogram method uses a common value found above the middle of the waveform. The units are expressed in volts.
AgilentU2701A Measurement VoltageLow	10	The voltage that corresponds to 0% when using the reference levels. The oscilloscope calculates this value using either the min/max or histogram methods. The min/max method uses the minimum value found. The histogram method uses a common value found below the middle of the waveform. The units are expressed in volts.
AgilentU2701A Measurement VoltageAverage	11	The arithmetic average in volts measured over the entire waveform. The units are expressed in volts.
AgilentU2701A Measurement WidthNeg	12	The length of time between the mid reference level points of a negative pulse in the waveform. The units are expressed in seconds.
AgilentU2701A Measurement WidthPos	13	The length of time between the mid reference level points of a positive pulse in the waveform. The units are expressed in seconds.
AgilentU2701A MeasurementDuty CycleNeg	14	The ratio of the WidthNeg to the Period of an integer number of cycles in the waveform expressed as a percentage.
AgilentU2701A MeasurementDuty CyclePos	15	The ratio of the WidthPos width to the Period of an integer number of cycles in the waveform expressed as a percentage.
AgilentU2701A Measurement Amplitude	16	The VoltageHigh less the VoltageLow expressed in volts over the entire waveform.
AgilentU2701A Measurement VoltageCycleRMS	17	The true root mean square voltage over an integer number of cycles in the waveform. The units are expressed in volts.
AgilentU2701A MeasurementOver Shoot	18	The relative waveform distortion that follows an edge transition.

5 Post Analysis

Member name	Value	Description
AgilentU2701A Measurement Preshoot	19	The relative waveform distortion that precedes an edge transition.
AgilentU2701A Measurement Phase	20	Phase.
AgilentU2701A Measurement Delay	21	Delay.
AgilentU2701A Measurement CrestFactor	22	Crest factor.
AgilentU2701A Measurement StandardDeviation	23	Standard deviation.
AgilentU2701A Measurement TimeAtMax	24	Time at maximum voltage.
AgilentU2701A Measurement TimeAtMin	25	Time at minimum voltage.

AgilentU2701ATimeOutEnum

Description

IVI Scope class-compliant values for *maxTime* parameter of the measurement Read and Fetch methods.

Members

Member name	Value	Description
AgilentU2701A TimeOut Immediate	0	This method returns immediately. If no measurement value exists, an error is returned.
AgilentU2701A TimeOutInfinite	-1	The method waits indefinitely for the measurement to complete.



6 Others

Calibration Interface commands starting on [page 156](#)

DriverOperation Interface commands starting on [page 160](#)

Identity Interface commands starting on [page 174](#)

SerialNumber [185](#)

This chapter describes the other commands used to program the U2701A/U2702A USB modular oscilloscopes over the remote interface. You can use the commands in this chapter to get and set some of the oscilloscope properties. You can also calibrate the instrument and perform various driver operations.



Calibrate

Type

Method

Function

Set

Description

This command calibrates the instrument. This method might take several minutes to complete.

Hierarchy

```
IAgilentU2701A
├── Calibration
│   └── Calibrate()
```

Example

```
Sub Main()
    ' Create an instance of the driver
    Dim Driver As New AgilentU2701A
    ' Calibrate Statement
    Driver.Calibration.Calibrate()
End Sub
```

Date

Type

Property

Function

Get

Description

This command returns the date the instrument was last calibrated.

Hierarchy

```
IAgilentU2701A
├── Calibration
│   └── Date
```

Return Format

String/BSTR

Example

```
Sub Main()
    ' Create an instance of the driver
    Dim Driver As New AgilentU2701A
    ' Date Statement
    Dim LastCalDate As String
    LastCalDate = Driver.Calibration.Date
End Sub
```

Label

Type

Property

Function

Get

Description

This command returns the label set during the last calibration.

Hierarchy

```
IAgilentU2701A
  └─ Calibration
     └─ Label
```

Return Format

String/BSTR

Example

```
Sub Main()
    ' Create an instance of the driver
    Dim Driver As New AgilentU2701A
    ' Label Statement
    Dim Label As String
    Label = Driver.Calibration.Label
End Sub
```

Time

Type

Property

Function

Get

Description

This command returns the time the instrument was last calibrated.

Hierarchy

```
IAgilentU2701A
├── Calibration
│   └── Time
```

Return Format

String/BSTR

Example

```
Sub Main()
    ' Create an instance of the driver
    Dim Driver As New AgilentU2701A
    ' Time Statement
    Dim LastCalTime As String
    LastCalTime = Driver.Calibration.Time
End Sub
```

Cache

Type

Property

Function

Get and Set

Description

Drivers may choose to always cache some instrument settings, never cache others, or optionally cache others to avoid unnecessary I/O activities to the instrument. If this command is set to `True`, the driver caches optionally cache instrument settings.

Hierarchy

```
IAgilentU2701A
├── DriverOperation
│   └── Cache
```

Return Format

Boolean

Example

```
Sub Main()
    ' Create an instance of the driver
    Dim Driver As New AgilentU2701A
    ' Cache Statement
    ' To Get Cache from the Instrument
    Dim Cache As Boolean
    Cache = Driver.DriverOperation.Cache
    ' To Set Cache eg. True
    Driver.DriverOperation.Cache = True
End Sub
```


ClearInterchangeWarnings

Type

Method

Function

Set

Description

This command clears the list of interchangeability warnings that the IVI specific driver maintains.

Hierarchy

```
IAgilentU2701A
├── DriverOperation
│   └── ClearInterchangeWarnings
```

Return Format

Boolean

Example

```
Sub Main()
    ' Create an instance of the driver
    Dim Driver As New AgilentU2701A
    ' Clear InterchangeWarnings Statement
    Driver.DriverOperation.ClearInterchangeWarnings()
End Sub
```

DriverSetup

Type

Property

Function

Get

Description

This command returns the driver setup string. It is either specified in the configuration store or passed in the *OptionString* parameter of the function. Driver setup is empty if the driver is not initialized.

Hierarchy

```
IAgilentU2701A
├── DriverOperation
│   └── DriverSetup
```

Return Format

String/BTSR

Example

```
Sub Main()
    ' Create an instance of the driver
    Dim Driver As New AgilentU2701A
    ' DriverSetup Statement
    Dim DriverSetup As String
    Cache = Driver.DriverOperation.Cache
    ' To Set Cache eg. True
    DriverSetup = Driver.DriverOperation.DriverSetup
End Sub
```

GetNextCoercionRecord

Type

Method

Function

Get

Description

This command returns the oldest record from the coercion record list. Records are only added to the list if [RecordCoercions](#) is set to True.

Hierarchy

```
IAgilentU2701A
├── DriverOperation
│   └── GetNextCoercionRecord()
```

Return Format

String/BTSR

Example

```
Sub Main()
    ' Create an instance of the driver
    Dim Driver As New AgilentU2701A
    ' GetNextCoercionRecord Statement
    Dim DriverSetup As String
    GetNextCoercionRecord =
        Driver.DriverOperation.GetNextCoercionRecord()
End Sub
```

GetNextInterchangeWarning

Type

Method

Function

Get

Description

This command returns the oldest warning from the interchange warning list. Records are only added to the list if [InterchangeCheck](#) is set to `True`.

Hierarchy

```
IAgilentU2701A
├── DriverOperation
│   └── GetNextInterchangeWarning()
```

Return Format

String/BTSR

Example

```
Sub Main()
    ' Create an instance of the driver
    Dim Driver As New AgilentU2701A
    ' GetNextInterchangeWarning Statement
    Dim GetNextInterchangeWarning As String
    GetNextInterchangeWarning =
        Driver.DriverOperation.GetNextInterchangeWarning()
End Sub
```

InterchangeCheck

Type

Property

Function

Get and Set

Description

If this command is set to `True`, the driver maintains a record of interchangeability warnings. If the driver does not support interchangeability checking, attempts to set `InterchangeCheck` to `True` returns an error.

Hierarchy

```
IAgilentU2701A
├── DriverOperation
│   └── InterchangeCheck
```

Return Format

Boolean

Example

```
Sub Main()
    ' Create an instance of the driver
    Dim Driver As New AgilentU2701A
    ' InterchangeCheck Statement
    ' To Get InterchangeCheck from the Instrument
    Dim InterchangeCheck As Boolean
    InterchangeCheck = Driver.DriverOperation.InterchangeCheck
    ' To Set InterchangeCheck eg. True
    Driver.DriverOperation.InterchangeCheck = True
End Sub
```

InvalidateAllAttributes

Type

Method

Function

Set

Description

This command invalidates all of the driver cached values.

Hierarchy

```
IAgilentU2701A
├── DriverOperation
│   └── InvalidateAllAttributes()
```

Return Format

Boolean

Example

```
Sub Main()
    ' Create an instance of the driver
    Dim Driver As New AgilentU2701A
    ' InvalidateAllAttributes Statement
    Driver.DriverOperation.InvalidateAllAttributes()
End Sub
```

IoResourceDescriptor

Type

Property

Function

Get

Description

This command returns the instrument resource descriptor. The resource descriptor specifies the connection to a physical device. It is either specified in the configuration store or passed in the *ResourceName* parameter of the [Initialize](#) function. It is empty if the driver is not initialized.

Hierarchy

```
IAgilentU2701A
├── DriverOperation
│   └── IoResourceDescriptor
```

Return Format

String/BSTR

Example

```
Sub Main()
    ' Create an instance of the driver
    Dim Driver As New AgilentU2701A
    ' IoResourceDescriptor Statement
    Dim IoResourceDescriptor As String
    IoResourceDescriptor =
        Driver.DriverOperation.IoResourceDescriptor
End Sub
```

LogicalName

Type

Property

Function

Get

Description

This command returns the instrument logical name. The logical name identifies a driver session in the configuration store. If logical name is not empty, the driver was initialized from the information in the driver session. If it is empty, the driver was initialized without using the configuration store.

Hierarchy

```
IAgilentU2701A
├── DriverOperation
│   └── LogicalName
```

Return Format

String/BSTR

Example

```
Sub Main()
    ' Create an instance of the driver
    Dim Driver As New AgilentU2701A
    ' IoResourceDescriptor Statement
    Dim LogicalName As String
    LogicalName = Driver.DriverOperation.LogicalName
End Sub
```


QueryInstrumentStatus

Type

Property

Function

Get and Set

Description

If this command is set to `True`, the driver queries the instrument status at the end of each method or property that performs I/O to the instrument. If an error is reported, use [ErrorQuery](#) to retrieve error messages one at a time from the instrument.

Hierarchy

```
IAgilentU2701A
├── DriverOperation
│   └── QueryInstrumentStatus
```

Return Format

Boolean

Example

```
Sub Main()
    ' Create an instance of the driver
    Dim Driver As New AgilentU2701A
    ' QueryInstrumentStatus Statement
    ' To Get QueryInstrumentStatus from the Instrument
    Dim QueryInstrumentStatus As Boolean
    QueryInstrumentStatus =
        Driver.DriverOperation.QueryInstrumentStatus
    ' To Set QueryInstrumentStatus eg. True
    Driver.DriverOperation.QueryInstrumentStatus = True
End Sub
```

RangeCheck

Type

Property

Function

Get and Set

Description

Drivers may choose to always validate some property or parameter values, never validate others, and optionally validate others, to avoid sending invalid commands to the instrument. If this command is set to `True`, the driver performs optional validations.

Hierarchy

```
IAgilentU2701A
├── DriverOperation
│   └── RangeCheck
```

Return Format

Boolean

Example

```
Sub Main()
    ' Create an instance of the driver
    Dim Driver As New AgilentU2701A
    ' RangeCheck Statement
    ' To Get RangeCheck from the Instrument
    Dim RangeCheck As Boolean
    RangeCheck = Driver.DriverOperation.RangeCheck
    ' To Set RangeCheck eg. True
    Driver.DriverOperation.RangeCheck = True
End Sub
```

RecordCoercions

Type

Property

Function

Get and Set

Description

If this command is set to `True`, the driver keeps a list of the value coercions it makes for *ViInt32* and *ViReal64* attributes. If the driver does not support coercion recording, attempts to set `RecordCoercions` to `True` will return an error.

Hierarchy

```
IAgilentU2701A
├── DriverOperation
│   └── RecordCoercions
```

Return Format

Boolean

Example

```
Sub Main()
    ' Create an instance of the driver
    Dim Driver As New AgilentU2701A
    ' RecordCoercions Statement
    ' To Get RecordCoercions from the Instrument
    Dim RecordCoercions As Boolean
    RecordCoercions = Driver.DriverOperation.RecordCoercions
    ' To Set RecordCoercions eg. True
    Driver.DriverOperation.RecordCoercions = True
End Sub
```

ResetInterchangeCheck

Type

Method

Function

Set

Description

This command resets the interchangeability checking algorithms of the driver so that methods and properties that were executed prior to calling this function have no affect on whether future calls to the driver will generate interchangeability warnings or not.

Hierarchy

```
IAgilentU2701A
├── DriverOperation
│   └── ResetInterchangeCheck()
```

Example

```
Sub Main()
    ' Create an instance of the driver
    Dim Driver As New AgilentU2701A
    ' ResetInterchangeCheck Statement
    Driver.DriverOperation.ResetInterchangeCheck()
End Sub
```

Simulate

Type

Property

Function

Get and Set

Description

If this command is set to `True`, the driver does not perform I/O to the instrument, and returns simulated values for output parameters instead.

Hierarchy

```
IAgilentU2701A
├── DriverOperation
│   └── Simulate
```

Return Format

Boolean

Example

```
Sub Main()
    ' Create an instance of the driver
    Dim Driver As New AgilentU2701A
    ' Simulate Statement
    ' To Get Simulate from the Instrument
    Dim Simulate As Boolean
    Simulate = Driver.DriverOperation.Simulate
    ' To Set Simulate eg. True
    Driver.DriverOperation.Simulate = True
End Sub
```

Description

Type

Property

Function

Get

Description

This command returns a brief description of the implementing component. Description is limited to 256 bytes.

Hierarchy

```
IAgilentU2701A
  | Identity
  | Description
```

Return Format

String/BSTR

Example

```
Sub Main()
    ' Create an instance of the driver
    Dim Driver As New AgilentU2701A
    ' Description Statement
    Dim Description As String
    Description = Driver.Identity.Description
End Sub
```

GroupCapabilities

Type

Property

Function

Get

Description

This command returns a comma-separated list of the class capability groups implemented by the driver. Capability group names are documented in the IVI class specifications. If the driver is not class compliant, the driver returns an empty string.

Hierarchy

```
IAgilentU2701A
├ Identity
└ GroupCapabilities
```

Return Format

String/BSTR

Example

```
Sub Main()
    ' Create an instance of the driver
    Dim Driver As New AgilentU2701A
    ' GroupCapabilities Statement
    Dim GroupCapabilities As String
    GroupCapabilities = Driver.Identity.GroupCapabilities
End Sub
```

Identifier

Type

Property

Function

Get

Description

This command returns the case-sensitive unique identifier of the implementing IVI-COM instrument driver.

Hierarchy

```
AgilentU2701A
  └ Identity
    └ Identifier
```

Return Format

String/BSTR

Example

```
Sub Main()
    ' Create an instance of the driver
    Dim Driver As New AgilentU2701A
    ' Identifier Statement
    Dim Identifier As String
    Identifier = Driver.Identity.Identifier
End Sub
```


InstrumentFirmwareRevision

Type

Property

Function

Get

Description

This command returns the firmware revision reported by the physical instrument. If [Simulate](#) is enabled or the instrument is not capable of reporting the firmware revision, a string is returned that explains the condition.

Hierarchy

```
IAgilentU2701A
├ Identity
└ InstrumentFirmwareRevision
```

Return Format

String/BSTR

Example

```
Sub Main()
    ' Create an instance of the driver
    Dim Driver As New AgilentU2701A
    ' InstrumentFirmwareRevision Statement
    Dim InstrumentFirmwareRevision As String
    InstrumentFirmwareRevision =
        Driver.Identity.InstrumentFirmwareRevision
End Sub
```

InstrumentManufacturer

Type

Property

Function

Get

Description

This command returns the name of the manufacturer reported by the physical instrument. If [Simulate](#) is enabled or the instrument is not capable of reporting the name of the manufacturer, a string is returned that explains the condition. InstrumentManufacturer is limited to 256 bytes.

Hierarchy

```
IAgilentU2701A
  | Identity
  | InstrumentManufacturer
```

Return Format

String/BSTR

Example

```
Sub Main()
    ' Create an instance of the driver
    Dim Driver As New AgilentU2701A
    ' InstrumentManufacturer Statement
    Dim InstrumentManufacturer As String
    InstrumentManufacturer =
        Driver.Identity.InstrumentManufacturer
End Sub
```

InstrumentModel

Type

Property

Function

Get

Description

This command returns the model number or name reported by the physical instrument. If [Simulate](#) is enabled or the instrument is not capable of reporting the model number or name, a string is returned that explains the condition. InstrumentModel is limited to 256 bytes.

Hierarchy

```
IAgilentU2701A
  | Identity
  | InstrumentModel
```

Return Format

String/BSTR

Example

```
Sub Main()
    ' Create an instance of the driver
    Dim Driver As New AgilentU2701A
    ' InstrumentModel Statement
    Dim InstrumentModel As String
    InstrumentModel = Driver.Identity.InstrumentModel
End Sub
```

Revision

Type

Property

Function

Get

Description

This command returns the revision of the implementing component. Revision is limited to 256 bytes.

Hierarchy

```
IAgilentU2701A
  | Identity
  | Revision
```

Return Format

String/BSTR

Example

```
Sub Main()
    ' Create an instance of the driver
    Dim Driver As New AgilentU2701A
    ' Revision Statement
    Dim Revision As String
    Revision = Driver.Identity.Revision
End Sub
```

SpecificationMajorVersion

Type

Property

Function

Get

Description

For IVI class-compliant drivers, this command returns the major version number of the instrument class specification. If the driver is not class compliant, the driver returns zero.

Hierarchy

```
IAgilentU2701A
├ Identity
└ SpecificationMajorVersion
```

Return Format

Long/Int32

Example

```
Sub Main()
    ' Create an instance of the driver
    Dim Driver As New AgilentU2701A
    ' SpecificationMajorVersion Statement
    Dim SpecificationMajorVersion As Int32
    SpecificationMajorVersion =
        Driver.Identity.SpecificationMajorVersion
End Sub
```

SpecificationMinorVersion

Type

Property

Function

Get

Description

For IVI class-compliant drivers, this command returns the minor version number of the instrument class specification. If the driver is not class compliant, the driver returns zero.

Hierarchy

```
IAgilentU2701A
  └ Identity
    └ SpecificationMinorVersion
```

Return Format

Long/Int32

Example

```
Sub Main()
    ' Create an instance of the driver
    Dim Driver As New AgilentU2701A
    ' SpecificationMinorVersion Statement
    Dim SpecificationMinorVersion As Int32
    SpecificationMinorVersion =
        Driver.Identity.SpecificationMinorVersion
End Sub
```

SupportedInstrumentModels

Type

Property

Function

Get

Description

This command returns a comma-separated list of instrument models that the IVI specific driver can control. The string does not include an abbreviation for the manufacturer if it is the same for all models.

Hierarchy

```
AgilentU2701A
  └ Identity
    └ SupportedInstrumentModels
```

Return Format

String/BSTR

Example

```
Sub Main()
    ' Create an instance of the driver
    Dim Driver As New AgilentU2701A
    ' SupportedInstrumentModels Statement
    Dim SupportedInstrumentModels As String
    SupportedInstrumentModels =
        Driver.Identity.SupportedInstrumentModels
End Sub
```

Vendor

Type

Property

Function

Get

Description

This command returns the name of the vendor that supplies the implementing component. Vendor is limited to 256 bytes.

Hierarchy

```
IAgilentU2701A
  | Identity
  | Vendor
```

Return Format

String/BSTR

Example

```
Sub Main()
    ' Create an instance of the driver
    Dim Driver As New AgilentU2701A
    ' Vendor Statement
    Dim Vendor As String
    Vendor = Driver.Identity.Vendor
End Sub
```


SerialNumber

Type

Property

Function

Get

Description

This command returns the instrument serial number.

Hierarchy


```
IAgilentU2701A
├ System
└ SerialNumber
```

Return Format

String

Example

```
Sub Main()
    ' Create an instance of the driver
    Dim Driver As New AgilentU2701A
    ' SerialNumber Statement
    Dim SerialNumber As String
    SerialNumber = Driver.System.SerialNumber
End Sub
```

7 Application Example

Introduction 188

Complete Example 190

This chapter contains an example program for the U2701A/U2702A USB modular oscilloscopes. The following program uses Microsoft Windows and Microsoft Visual Basic .Net (2003 and later). Refer to the instruction manual of Visual Basic .Net for further details about Visual Basic .Net.



Introduction

This section describes how the AgilentU2701A IVI driver is used for Visual Basic .Net (2003 and later). All explanations will be using Console Application as the project.

Referencing the Driver

In order to access AgilentU2701A IVI driver interface, a reference to the driver DLL must be created by following the steps listed below:

- 1 In the Solution Explorer, right-click your project name and select **Add Reference**.
- 2 Click the **COM** tab.
- 3 Select the **IVI AgilentU2701A 1.0 Type Library** and click **OK**.
- 4 The IVI AgilentU2701A 1.0 Type Library should now appear under the Reference tab by right-clicking your project name and selecting Properties.

All data types (interfaces and enums) are located under namespaces. Usually namespace qualified name must be used, but the “Imports” statement allows the type name to be used directly.

```
Imports System
Imports System.Runtime.InteropServices
Imports Ivi.Driver
Imports Ivi.Scope
Imports Agilent.AgilentU2701A.Interop
```

Creating an Instance


Create an instance of the Agilent U2701A IVI-COM driver.

```
' Create an instance of the driver
Dim Driver As New AgilentU2701A
```

Initializing the Driver

Calling Initialize will establish a connection to Agilent U2701A. You can get your resource name of your instrument by using the Agilent Connection Expert. Please refer to the “Initialize” on page 29 for a more detailed explanation.

This is an example to show you how to get your module resource name by using Agilent Connection Expert.



```
' Initialize the Driver
```

```
Driver.Initialize("USB0::2391::10520::MY48151002::0::INSTR",  
True, True, " ")
```

Calling Close is required to release the driver object.

```
' Close the Driver Object
```

```
Driver.Close()
```

Complete Example

This section illustrates a complete example covering the steps needed to fetch the instrument identity, reset the instrument, automatically scale the instrument, conducting a simple measurement, and finally acquiring and saving the waveform data. All the steps taken are commented in this example program.

```
Imports System
Imports System.Runtime.InteropServices
Imports System.IO
Imports Ivi.Driver
Imports Ivi.Scope
Imports Agilent.AgilentU2701A.Interop

Module Module1

    Sub Main()

        Try

            ' Create the instance of the driver
            Dim Driver As New AgilentU2701A

            ' Initialize the Driver
            Driver.Initialize("USB0::2391::10520::MY48151002::0::INSTR", False,
                False, "")

            ' Get Instrument Identity property
            Dim InstrumentModel As String
            InstrumentModel = Driver.Identity.InstrumentModel
            Console.WriteLine("Instrument Model: {0}", InstrumentModel)

            Dim InstrumentManufacturer As String
            InstrumentManufacturer = Driver.Identity.InstrumentManufacturer
            Console.WriteLine("Instrument Manufacturer: {0}",
                InstrumentManufacturer)

        End Try
    End Sub
End Module
```

```

Dim Revision As String
Revision = Driver.Identity.Revision
Console.WriteLine("Revision: {0}", Revision)

' Set TimeoutMilliseconds = 30000 (30 seconds)
Driver.System.TimeoutMilliseconds = 30000
' Reset U2701A
Driver.Utility.Reset()
Console.WriteLine("Reset Instrument Done")

' Auto Scale U2701A
Driver.Measurements.AutoSetup()
Console.WriteLine("Auto Scale Done")

' Measure Frequency signal input from Channel 1
Dim CH1Name As String = Driver.Channels.Name(1)
Dim FrequencyMeasured As Double

Driver.Measurements.Item(CH1Name).ReadWaveformMeasurement(AgilentU2701AMeasurementEnum.AgilentU2701AMeasurementFrequency, 5000,
    FrequencyMeasured)
Console.WriteLine("Frequency Measured: {0} Hz", FrequencyMeasured)

' Waveform Acquisition
Dim RecordLength As Int32 = Driver.Acquisition.RecordLength
Dim WaveformArray() As Double
Dim XIncrement As Double
Dim InitialX As Double
Dim XValue As Double = 0
Dim waveformText As String = ""
ReDim WaveformArray(RecordLength - 1)

Driver.Measurements.Item(CH1Name).ReadWaveform(5000, WaveformArray,
    InitialX, XIncrement)
Console.WriteLine("Initial X Value: {0}", InitialX)
Console.WriteLine("X Increment Value: {0}", XIncrement)
Console.WriteLine("WaveformArray: ")

```

7 Application Example

```
Dim i As Int32 = 0
While i < RecordLength
    XValue = InitialX + i*XIncrement
    Console.WriteLine("{0}, {1}" + vbCrLf, XValue, WaveformArray(i))
    waveformText += XValue.ToString("F6") + vbTab +
        WaveformArray(i).ToString("F4") + vbCrLf
    i = i + 1
End While
' Create a writer and open the file
Dim tw As TextWriter
tw = New StreamWriter("C:\waveform.txt")

' Write the text stream to file
tw.Write(waveformText)

' Close the stream
tw.Close()

' Read instrument error queue until its empty
Dim ErrorCode = -1
Dim ErrorMessage = ""

Console.WriteLine()
While ErrorCode <> 0
    Driver.Utility.ErrorQuery(ErrorCode, ErrorMessage)
    Console.WriteLine("ErrorQuery: {0}, {1}", ErrorCode, ErrorMessage)
End While

' Close the Driver Object
Driver.Close()
Catch ex As Exception
    Console.WriteLine(ex.Message)

End Try

Console.WriteLine("Done - Press Enter to Exit")
Console.ReadLine()
```



```
End Sub
```

```
End Module
```

7 Application Example

Command Quick Reference

Root keyword	Second-level	Third-level	Fourth-level	Page
IAgilentU2701A	Acquisition	ConfigureRecord		See page 100
		Interpolation		See page 102
		NumberOfAverages		See page 104
		RecordLength		See page 105
		SampleMode		See page 106
		SampleRate		See page 107
		StartTime		See page 108
		TimePerRecord		See page 109
		Type		See page 112
	Calibration	Calibrate		See page 156
		Date		See page 157
		Label		See page 158
		Time		See page 159
	Channels	Count		See page 12
			Item	BandwidthLimit
			Configure	See page 15
			Coupling	See page 17
			Enabled	See page 19
			Offset	See page 21
			ProbeAttenuation	See page 23
			Range	See page 25
	Name		See page 27	
Close			See page 28	

Root keyword	Second-level	Third-level	Fourth-level	Page	
IAgilentU2701A	DriverOperation	Cache		See page 160	
		ClearInterchange Warnings		See page 161	
		DriverSetup		See page 162	
		GetNextCoercion Record		See page 163	
		GetNextInterchange Warning		See page 164	
		InterchangeCheck		See page 165	
		InvalidateAllAttributes		See page 166	
		IoResourceDescriptor		See page 167	
		LogicalName		See page 168	
		QueryInstrumentStatus		See page 169	
		RangeCheck		See page 170	
		RecordCoercions		See page 171	
		ResetInterchange Check		See page 172	
		Simulate		See page 173	
		Identity	Description		See page 174
			GroupCapabilities		See page 175
			Identifier		See page 176
InstrumentFirmware Revision			See page 177		
Instrument Manufacturer			See page 178		
InstrumentModel			See page 179		
Revision			See page 180		
SpecificationMajor Version		See page 181			

Root keyword	Second-level	Third-level	Fourth-level	Page	
IAgilentU2701A	Identity	SpecificationMinor Version		See page 182	
		SupportedInstrument Models		See page 183	
		Vendor		See page 184	
	Initialize			See page 29	
	Initialized			See page 31	
	Measurements	Abort			See page 118/130
		AutoSetup			See page 119/131
		Count			See page 120/132
		Initiate			See page 121/133
		IsWaveformElement Invalid			See page 122/134
		Item	FetchWaveform		See page 124/136
			FetchWaveform Measurement		See page 138
			ReadWaveform		See page 126/142
		ReadWaveform Measurement		See page 144	
		MathFunction		See page 146	
	Name		See page 147		
	Status		See page 148		
Status	Clear			See page 68	
	ConfigureService Request			See page 69	
	Preset			See page 71	
	Register			See page 72	
	SerialPoll			See page 74	

Root keyword	Second-level	Third-level	Fourth-level	Page		
IAgilentU2701A	System	SerialNumber		See page 75/185		
		TimeoutMilliseconds		See page 75		
		WaitForOperationComplete		See page 77		
	Trigger	Configure			See page 32	
			Coupling		See page 33	
			Edge	Configure	See page 35	
		Glitch		Slope	See page 37	
				Condition	See page 39	
				Configure	See page 41	
		Holdoff		Polarity	See page 43	
				Width	See page 45	
					See page 46	
				Modifier	See page 47	
				Level	See page 49	
				Source	See page 50	
		TV	Status			See page 51
					Configure	See page 52
					Event	See page 54
			Width		LineNumber	See page 56
					SignalFormat	See page 57
					Type	See page 59
	ThresholdHigh			Condition	See page 60	
				Configure	See page 62	
				Polarity	See page 64	

Root keyword	Second-level	Third-level	Fourth-level	Page
IAgilentU2701A	Trigger	Width	ThresholdLow	See page 67
	Utility	Disable		See page 78
		ErrorQuery		See page 79
		LockObject		See page 80
		Reset		See page 81
		ResetWithDefaults		See page 82
		SelfTest		See page 83
		UnlockObject		See page 85

Enumeration Quick Reference

Enumeration members	Page
AgilentU2701AAcquisitionStatusEnum	See page 114
AgilentU2701AAcquisitionTypeEnum	See page 115
AgilentU2701AGlitchConditionEnum	See page 86
AgilentU2701AGlitchPolarityEnum	See page 87
AgilentU2701AInterpolationEnum	See page 116
AgilentU2701AMathOperationEnum	See page 149
AgilentU2701AMeasurementEnum	See page 150
AgilentU2701ASampleModeEnum	See page 116
AgilentU2701ASRQReasonEnum	See page 87
AgilentU2701AStatusRegisterEnum	See page 89
AgilentU2701AStatusSubRegisterEnum	See page 90
AgilentU2701ATimeOutEnum	See page 153
AgilentU2701ATriggerCouplingEnum	See page 91
AgilentU2701ATriggerModifierEnum	See page 91
AgilentU2701ATriggerSlopeEnum	See page 92
AgilentU2701ATriggerTypeEnum	See page 93
AgilentU2701ATVSignalFormatEnum	See page 94
AgilentU2701ATVTriggerEventEnum	See page 95
AgilentU2701AVerticalCouplingEnum	See page 96
AgilentU2701AWidthConditionEnum	See page 97
AgilentU2701AWidthPolarityEnum	See page 97

Appendix

Property	Possible values		
IAgilentU2701AAcquisition.NumberOfAverages	Values (Int32)		
	1 - 999		
IAgilentU2701AAcquisition.StartTime IAgilentU2701AAcquisition.TimePerRecord	Time/Div	TimePerRecord	StartTime
	1 ns	10 ns	-5 ns - 5 ns
	2 ns	20 ns	-10 ns - 10 ns
	5 ns	50 ns	-25 ns - 25 ns
	10 ns	100 ns	-50 ns - 50 ns
	20 ns	200 ns	-100 ns - 100 ns
	50 ns	500 ns	-250 ns - 250 ns
	100 ns	1 μ s	-500 ns - 500 ns
	200 ns	2 μ s	-1 μ s - 1 μ s
	500 ns	5 μ s	-2.5 μ s - 2.5 μ s
	1 μ s	10 μ s	-5 μ s - 5 μ s
	2 μ s	20 μ s	-10 μ s - 10 μ s
	5 μ s	50 μ s	-25 μ s - 25 μ s
	10 μ s	100 μ s	-50 μ s - 50 μ s
	20 μ s	200 μ s	-100 μ s - 100 μ s
	50 μ s	500 μ s	-250 μ s - 250 μ s
	100 μ s	1 ms	-500 μ s - 500 μ s
	200 μ s	2 ms	-1 ms - 1 ms
	500 μ s	5 ms	-2.5 ms - 2.5 ms
	1 ms	10 ms	-5 ms - 5 ms
	2 ms	20 ms	-10 ms - 10 ms
	5 ms	50 ms	-25 ms - 25 ms
	10 ms	100 ms	-50 ms - 50 ms
	20 ms	200 ms	-100 ms - 100 ms
	50 ms	500 ms	-250 ms - 250 ms
100 ms	1 s	-500 ms - 500 ms	

IAgilentU2701AAcquisition.StartTime IAgilentU2701AAcquisition.TimePerRecord	Time/Div	TimePerRecord	StartTime
	200 ms	2 s	-1 s - 1 s
	500 ms	5 s	-2.5 s - 2.5 s
	1 s	10 s	-5 s - 5 s
	2 s	20 s	-10 s - 10 s
	5 s	50 s	-25 s - 25 s
	10 s	100 s	-50 s - 50 s
	20 s	200 s	-100 s - 100 s
	50 s	500 s	-250 s - 250 s
IAgilentU2701AChannels.Item	Name (String)		
	Channel1		
	Channel2		
	MathChannel		
IAgilentU2701AChannel.ProbeAttenuation	Value (double)		
	1		
	10		
	100		
IAgilentU2701AChannel.Offset IAgilentU2701AChannel.Range	Volt/Div	Voltage Range (Attenuation = 1x)	Offset
	2 mV	16 mV	-8 mV - 8 mV
	5 mV	40 mV	-20 mV - 20 mV
	10 mV	80 mV	-40 mV - 40 mV
	20 mV	160 mV	-80 mV - 80 mV
	50 mV	400 mV	-200 mV - 200 mV
	100 mV	800 mV	-400 mV - 400 mV
	200 mV	1.6 V	-800 mV - 800 mV
	500 mV	4 V	-2 V - 2 V
	1 V	8 V	-4 V - 4 V
	2 V	16 V	-8 V - 8 V
	5 V	40 V	-20 V - 20 V
IAgilentU2701ATriggerGlitch.Width	Condition LessThan (Value)	Condition GreaterThan (Value)	
	> 7 ns	> 15 ns	

IAgilentU2701ATrigger.Holdoff	Value (Double)
	> 59 ns
IAgilentU2701ATrigger.Source	Value (String)
	Channel1
	Chan1
	CHANNEL1
	Channel2
	Chan2
	CHANNEL2
	Ext
	EXT
	IAgilentU2701ATriggerTv.LineNumber
1 - 263	
IAgilentU2701ATriggerWidth.ThresholdHigh	Value (Double)
	> 15 ns
IAgilentU2701ATriggerWidth.ThresholdLow	Value (Double)
	> 7 ns

www.agilent.com

Contact us

To obtain service, warranty or technical assistance, contact us at the following phone or fax numbers:

United States:

(tel) 800 829 4444 (fax) 800 829 4433

Canada:

(tel) 877 894 4414 (fax) 800 746 4866

China:

(tel) 800 810 0189 (fax) 800 820 2816

Europe:

(tel) 31 20 547 2111

Japan:

(tel) (81) 426 56 7832 (fax) (81) 426 56 7840

Korea:

(tel) (080) 769 0800 (fax) (080) 769 0900

Latin America:

(tel) (305) 269 7500

Taiwan:

(tel) 0800 047 866 (fax) 0800 286 331

Other Asia Pacific Countries:

(tel) (65) 6375 8100 (fax) (65) 6755 0042

Or visit Agilent World Wide Web at:

www.agilent.com/find/assist

Product specifications and descriptions in this document are subject to change without notice. Always refer to Agilent Web site for the latest revision.

© Agilent Technologies, Inc., 2009 — 2012

Third Edition, August 13, 2012
U2702-90035



Agilent Technologies